

---

# Intel® Trace Collector 7.1

## User's Guide

---

Copyright © 1996-2008, Intel Corporation.  
All Rights Reserved  
Document number: 318119-001  
World Wide Web: <http://www.intel.com>



---

## Disclaimer and Legal Information

INFORMATION IN THIS DOCUMENT IS PROVIDED IN CONNECTION WITH INTEL PRODUCTS. NO LICENSE, EXPRESS OR IMPLIED, BY ESTOPPEL OR OTHERWISE, TO ANY INTELLECTUAL PROPERTY RIGHTS IS GRANTED BY THIS DOCUMENT. EXCEPT AS PROVIDED IN INTEL'S TERMS AND CONDITIONS OF SALE FOR SUCH PRODUCTS, INTEL ASSUMES NO LIABILITY WHATSOEVER, AND INTEL DISCLAIMS ANY EXPRESS OR IMPLIED WARRANTY, RELATING TO SALE AND/OR USE OF INTEL PRODUCTS INCLUDING LIABILITY OR WARRANTIES RELATING TO FITNESS FOR A PARTICULAR PURPOSE, MERCHANTABILITY, OR INFRINGEMENT OF ANY PATENT, COPYRIGHT OR OTHER INTELLECTUAL PROPERTY RIGHT.

UNLESS OTHERWISE AGREED IN WRITING BY INTEL, THE INTEL PRODUCTS ARE NOT DESIGNED NOR INTENDED FOR ANY APPLICATION IN WHICH THE FAILURE OF THE INTEL PRODUCT COULD CREATE A SITUATION WHERE PERSONAL INJURY OR DEATH MAY OCCUR.

Intel may make changes to specifications and product descriptions at any time, without notice. Designers must not rely on the absence or characteristics of any features or instructions marked "reserved" or "undefined." Intel reserves these for future definition and shall have no responsibility whatsoever for conflicts or incompatibilities arising from future changes to them. The information here is subject to change without notice. Do not finalize a design with this information.

The products described in this document may contain design defects or errors known as errata which may cause the product to deviate from published specifications. Current characterized errata are available on request.

Contact your local Intel sales office or your distributor to obtain the latest specifications and before placing your product order.

Copies of documents which have an order number and are referenced in this document, or other Intel literature, may be obtained by calling 1-800-548-4725, or by visiting Intel's Web Site.

Intel, Itanium, Pentium, VTune, and Xeon are trademarks of Intel Corporation in the U.S. and other countries.

\* Other names and brands may be claimed as the property of others.

Copyright © 1996-2008, Intel Corporation. All rights reserved.

This product includes software developed by the University of California, Berkley and its contributors, and software derived from the Xerox Secure Hash Function. It includes software developed by the University of Tennessee, see appendix A for details. It includes libraries developed and © by SGI and others. They are licensed under the GNU Lesser General Public License (LGPL) or Runtime General Public License and their source code can be downloaded from '<ftp://ftp.i kn.intel.com/pub/opensource>'.



# Contents

<b>Contents</b>	<b>I</b>
<b>1 Introduction</b>	<b>1</b>
1.1 What is the Intel® Trace Collector (ITC)?	1
1.2 System Requirements and Supported Features	1
1.3 Multithreading	3
1.4 About this Manual	3
<b>2 Installation</b>	<b>5</b>
<b>3 How to Use ITC</b>	<b>7</b>
3.1 Tracing MPI Applications	7
3.2 Tracing shmexec Programs with ITC	12
3.3 Single-process Tracing	15
3.4 Compiler-driven Subroutine Instrumentation	16
3.5 Tracing of Binaries and Binary Instrumentation	17
3.6 Multithreaded Tracing	22
3.7 Recording Statistical Information	22
3.8 Recording Source Location Information	24
3.9 Recording Hardware Performance Information	25
3.10 Recording OS Counters	26
3.11 Using the Dummy Libraries	27
3.12 Using the Shared Libraries	27
3.13 Tracing Library Calls	28
<b>4 Correctness Checking</b>	<b>31</b>
4.1 Overview	31
4.2 Usage	32
4.3 Error Detection	36



---

<b>5</b>	<b>Time Stamping</b>	<b>47</b>
5.1	Clock Synchronization . . . . .	48
5.2	Choosing a Timer . . . . .	48
<b>6</b>	<b>Tracing of Distributed Applications</b>	<b>57</b>
6.1	Design . . . . .	57
6.2	Using VTserver . . . . .	58
6.3	Running without VTserver . . . . .	59
6.4	Spawning Processes . . . . .	59
6.5	Tracing Events . . . . .	60
6.6	Usage . . . . .	60
6.7	Signals . . . . .	60
6.8	Examples . . . . .	60
<b>7</b>	<b>Structured Tracefile Format</b>	<b>63</b>
7.1	Introduction . . . . .	63
7.2	STF Components . . . . .	64
7.3	Single-File STF . . . . .	65
7.4	Configuring STF . . . . .	65
<b>8</b>	<b>User-level Instrumentation with the API</b>	<b>71</b>
8.1	The ITC API . . . . .	71
8.2	Initialization, Termination and Control . . . . .	73
8.3	Defining and Recording Source Locations . . . . .	77
8.4	Defining and Recording Functions or Regions . . . . .	80
8.5	Defining and Recording Overlapping Scopes . . . . .	85
8.6	Defining Groups of Processes . . . . .	86
8.7	Defining and Recording Counters . . . . .	88
8.8	Recording Communication Events . . . . .	90
8.9	Additional API Calls in libVTcs . . . . .	94
8.10	C++ API . . . . .	97
<b>9</b>	<b>ITC Configuration</b>	<b>103</b>
9.1	Configuring Intel(R) Trace Collector . . . . .	103
9.2	Specifying Configuration Options . . . . .	103
9.3	Configuration Format . . . . .	103
9.4	Syntax of Parameters . . . . .	104
9.5	Supported Directives . . . . .	104



## CONTENTS

---

9.6 How to Use the Filtering Facility . . . . .	116
9.7 The Protocol File . . . . .	117
<b>A Copyright and Licenses</b>	<b>119</b>



# Chapter 1

## Introduction

### 1.1 What is the Intel® Trace Collector (ITC)?

The Intel® Trace Collector for MPI applications produces tracefiles that can be analyzed with the Intel® Trace Analyzer (ITA) performance analysis tool. Some ITC versions are also able to trace non-MPI applications, like socket communication in distributed applications or plain serial programs. It was formerly known as Vampirtrace.

In MPI it records all calls to the MPI library and all transmitted messages, and allows arbitrary user defined events to be recorded. Instrumentation can be switched on or off at runtime, and a powerful filtering mechanism helps to limit the amount of the generated trace data.

ITC is an add-on for existing MPI implementations; using it merely requires relinking the application with the ITC profiling library (see section 3.1.1). This will enable the tracing of all calls to MPI routines, as well as all explicit message-passing. On some platforms, calls to user-level subroutines and functions will also be recorded. Shared libraries (section 3.12) and binary instrumentation (section 3.4.4) allow to attach the Trace Collector without and explicit linking step.

To define and trace user-defined events, or to use the profiling control functions, calls to the ITC API (see section 8) have to be inserted into the application's source code. This implies a recompilation of all affected source modules.

A special “dummy” version of the profiling libraries containing empty definitions for all ITC API routines can be used to “switch off” tracing just by relinking (see section 3.1.3).

### 1.2 System Requirements and Supported Features

It is compatible with all other MPI implementations that use the same binary interface. If in doubt, lookup your hardware platform and MPI in the ITC system requirements list at <http://www.intel.com/software/products/cluster>. If your combination is not listed, you can check compatibility yourself by compiling and running the `examples/mpiconstants.c` program with your MPI. If any value of the constants in the output differs from the ones given below, then this version of ITC will not work:



	intel64-lin-impi3 intel64-win-impi32 intel64-win-impi64 ia32-lin-impi3 ia64-lin-impi3	intel64-lin-mpich ia64-lin-mpich	ia32-lin-mpich	ia64-lin-mpt
<i>sizeof(MPI_Datatype)</i>	4	4	4	4
<i>sizeof(MPI_Comm)</i>	4	4	4	4
<i>sizeof(MPI_Request)</i>	4	8	4	4
<i>MPI_CHAR</i>	1275068673	1	1	1
<i>MPI_BYTE</i>	1275068685	3	3	27
<i>MPI_SHORT</i>	1275068931	4	4	2
<i>MPI_INT</i>	1275069445	6	6	3
<i>MPI_FLOAT</i>	1275069450	10	10	9
<i>MPI_DOUBLE</i>	1275070475	11	11	10
<i>MPI_COMM_WORLD</i>	1140850688	91	91	1
<i>MPI_COMM_SELF</i>	1140850689	92	92	2
<i>MPI_STATUS_SIZE</i>	5	4	4	6
<i>MPI_SOURCE</i>	8	4	4	0
<i>MPI_TAG</i>	12	8	8	4
<i>MPI_ERROR</i>	16	12	12	8

The following features are supported:

Feature	Description
Thread-safety	<a href="#">1.3</a>
MPI tracing	<a href="#">3.1</a>
• IO	<a href="#">ROMIO, 3.1.8</a>
• MPI One-Sided Communication	<a href="#">3.1.9</a>
• MPI-2	not supported
• fail-safe	<a href="#">3.1.7</a>
• correctness checking	<a href="#">4</a>
SHMEM tracing	<a href="#">3.2</a>
Single-process tracing	<a href="#">3.3</a>
Tracing of Distributed Applications	<a href="#">6</a>
Subroutine tracing	<a href="#">3.4</a>
Tracing of Binaries without Recompilation	<a href="#">3.4.4</a>
Counter tracing	API in <a href="#">8.7</a>
Automatic Counter tracing of OS Activity	<a href="#">3.10</a>
Automatically Recording Source Location Information	<a href="#">3.8</a> (requires compiler support)
Manually Recording Source Location Information	API in <a href="#">8.3</a>
Recording Statistical Information	<a href="#">3.7</a>
Tracing Libraries at Different Levels of Detail	<a href="#">3.13</a>
Nonblocking Flushing	<a href="#">MEM-FLUSHBLOCKS</a>

Most of these features are implemented in the ITC libraries, while some are provided by utilities. Here is a list of what the different components do:





## 1.3. MULTITHREADING

Component	Usage
libVTnull	Dummy implementation of API (3.11)
libVT	MPI tracing (3.1) SHMEM tracing (3.2)
libVTfs	fail-safe MPI tracing (3.1.7) fail-safe SHMEM tracing (3.2)
libVTmc	correctness checking(4)
libVTcs	Tracing of Distributed Applications and Single-processes (6, 3.3)
VT_sample	Automatic Counter tracing with PAPI and getrusage() (3.9)
stftool	Manipulation of trace files (7.4.1)
xstftool/expandvtlog.pl	Conversion of trace files into readable format (7.4.2)
itcpin	Tracing of Binaries without Recompile (3.4.4)

## 1.3 Multithreading

This version of the ITC library is thread-safe in the sense that all of its API functions can be called by several threads at the same time. Some API functions can really be executed concurrently, others protect global data with POSIX mutexes. More information on tracing multithreaded applications is found in section 3.6.

## 1.4 About this Manual

This manual describes how to use Intel® Trace Collector. On Linux\*, Some of the text is also provided as man pages for easier reading in a shell, for example, the ITC API calls (man [VT\\_enter](#)) and the ITC configuration (man [VT\\_CONFIG](#)). To access the man pages, follow the instructions in the next chapter.

In the PDF version of the manual all special ITC terms and names are hyperlinks that take you to the definition of the word. The documentation is platform-independent, which means that the text and even whole sections may not be applicable for platforms. Hence, if you move between different platforms certain features may work differently.

This manual tries to cover as much as possible independent on the diverse platforms it supports. Linux\* and Microsoft\* Windows\* frequently have different styles in passing parameters. In particular parameters to compilers are not consistent between the two operating systems. This manual follows the nomenclature used on Linux. Here is a list of the most important differences and how they are mapped from Linux style to the Microsoft\* Windows\* way:

Linux*	Microsoft* Windows*
-L<path>	-LIBPATH:<path>
-l<library>	<library>.lib
<directory>/<file>	<directory>\<file>





---

## Chapter 2

# Installation

On Linux\*: After unpacking the ITC archive in a directory of your choice read the file 'relnotes.txt' for information on how to install Intel® Trace Collector. On Microsoft\* Windows\*: execute the installer file setup.exe and follow the instructions given in the installation wizard.

In order to enable the software, Intel will issue you a license key. The license key is a simple text file containing details of the software that will be enabled. An evaluation license key contains a time limited license.

If called without a valid license, or with invalid settings of the above environment variable, installation aborts with an error message like the following one:

```
Checking for flexlm license
Feature to check out: TRACE_COLLECTOR
```

```
Error: A license for ITrColL could not be obtained (-1,359,2).
```

```
Is your license file in the right location and readable?
The location of your license file has to be specified via
the $INTEL_LICENSE_FILE environment variable.
```

```
License file(s) used were (in this order):
```

```
Visit http://support.intel.com/support/performance/tools/support.htm
if you require technical assistance.
```

```
FLEX_CHECKOUT test failed to acquire license (rc=-1)
```

License management has to be transparent, but if you have any problems during installation, submit an issue to Intel® Premier Support or send an email to [tracetools @ intel.com](mailto:tracetools@intel.com).

To acquire a demo license, use Intel Premier Support or contact [tracetools@intel.com](mailto:tracetools@intel.com). This email address can also be used to find out how to purchase the product. At <http://www.intel.com/software/products/cluster> you will also find a list of your local sales channel.

The installer creates `itacvars.sh` (for shells with Bourne syntax) and `itacvars.csh` (for shells with csh syntax) on Linux systems. On Microsoft\* Windows\* systems you will find an `itacvars.bat` batch script. Sourcing the correct file in a shell (with `. itacvars.sh`, or `source itacvars.csh` or `itacvars.bat` respectively) will update `$LD_LIBRARY_PATH` and `$PATH` as well as set additional environment variables.



**VT\_ROOT** points to the root of the ITC installation. It is used to find the ITC include and library files when compiling programs in the example makefile (Example: for using it with `'-I$(VT_ROOT)'`).

**VT\_LIB\_DIR** points to the directory containing the static ITC libraries. It might be useful to create Makefiles or shorter linkage commands when using `'-L'`.

**VT\_SLIB\_DIR** (resp. **VT\_DLL\_DIR** on Microsoft\* Windows\*) points to the directory containing the dynamic ITC libraries. It might be useful to create Makefiles or shorter linkage commands when using `'-L'`.

**VT\_ADD\_LIBS** lists libraries ITC is dependent on and needs to be linked against when using ITC.

**VT\_MPI** points to the currently selected MPI implementation as used by **VT\_LIB\_DIR** and **VT\_SLIB\_DIR**.

**VT\_MPI\_DLL** (Microsoft\* Windows\* version only) name of the MPI dll to be loaded by an ITC dll. If the Fortran interface of MPI is involved and MPI offers this in a separate dll (e.g. MPICH2), it has to be specified via **VT\_FMPI\_DLL**.

The `itavars` scripts accept an optional argument to specify the desired MPI implementation you intend to work with: on Linux\* `impi2`, `impi3`, `mpich` or `mpt` (e.g. `'source itacvars.csh impi3'` selects Intel® MPI Library version 3), on Microsoft\* Windows\* `impi32`, `impi64`, `mpich2_32`, `mpich2_64` (e.g. `itacvars.bat impi64` selects the 64-bit version of Intel® MPI). This mechanism allows you to switch between different MPI implementations. Without an argument the scripts assume the MPI implementation you selected the default at installation time (Intel® MPI on Microsoft\* Windows\*).

It is possible to install several different ITC packages in parallel on the same machine by using different directories. Overwriting an old installation with a new one is not recommended, because this will not ensure that obsolete old files are removed. A single dot `"."` can be used to install in the directory where the archive was unpacked.

In order to use ITC on a cluster of machines you can either install ITC once in a shared directory which is mounted at the same location on all nodes, or you can install it separately on each node in a local directory. Neither method has a clear advantage when it comes to runtime performance. Root privileges are only needed if writing into the desired install directory requires them.

For using shared libraries (section 3.12 or in particular for binary instrumentation (section 3.4.4)) the installation path must be the same on all nodes.

On Microsoft\* Windows\* Compute Cluster Server most of this is handled by OS provided mechanisms. For Linux\* there is a mechanism for unattended mass installations in clusters. It consists of the following steps:

1. Start the install script with the option `--duplicate`. It will ask the usual questions and install ITC, but in addition to that it will create a file called `itc_<platform>_<version>_SilentInstall.ini` in the current directory or, if that directory is not writable, `/tmp/itc_<platform>_<version>/SilentInstall.ini`.  
Alternatively you can modify the existing `SilentInstallConfigFile.ini`. It is necessary to acknowledge the End User License Agreement by editing that file and replacing `ITC_EULA=reject` with `ITC_EULA=accept`.
2. Run the install script on each node with the option `--silent <.ini file>`. This will install ITC without further questions using the install options from that `.ini` file. Only error messages will be printed, all the normal progress messages are suppressed.

## Chapter 3

# How to Use ITC

### 3.1 Tracing MPI Applications

Using Intel® Trace Collector for MPI is straightforward: relink your MPI application with the appropriate profiling library and execute it following the usual procedures of your system. This will generate a tracefile suitable for use with ITA, including records of all calls to MPI routines as well as all point-to-point and collective communication operations performed by the application.

If you wish to get more detailed information about your application, the Trace Collector provides several methods to instrument your application: Binary instrumentation (see section 3.4.4), compiler instrumentation (see section 3.4) and source code instrumentation through its API (see section 8). This will allow arbitrary user-defined events to be traced; in practice, it is often very useful to record your applications entry and exit to/from subroutines or regions within large subroutines.

The following sections explain how to compile, link and execute MPI applications with ITC; if your MPI is different from the one ITC was compiled for, or is setup differently, then the paths and options may vary. These sections assume that you know how to compile and run MPI applications on your system, so before trying to follow the instructions below, read the relevant system documentation.

#### 3.1.1 Compiling MPI Programs with ITC

Source files without calls to the ITC API can be compiled with the usual methods and without any special precautions.

Source files that do contain calls to the ITC API need to include the appropriate header files: VT.h for C and C++ and VT.inc for Fortran.

To compile these source files, the path to the ITC header files have to be passed to the compiler. On most systems, this is done with the -I flag, say with -I\$(VT\_ROOT)/include.

#### 3.1.2 Linking MPI Programs with ITC

ITC library libVT.a contains entry points for all MPI routines. They have to be linked against your application object files before your system's MPI library. ITC requires a set of additional libraries. For your convenience the itacvars-scripts set the environment variables \$VT\_ADD\_LIBS and \$VT\_LIB\_DIR accordingly. The most easiest way is to use the compile scripts provided by



the Intel® MPI Library: simply use the command line argument '-trace'. It does everything for you. All it requires is having sourced/executed the respective itacvars script.

In general, a correct link line is achieved as follows (after sourcing/executing the appropriate itacvars script):

Linux:

```
mpicc ctest.o -L$VT_LIB_DIR -lVT $VT_ADD_LIBS -o ctest
mpif77 ftest.o -L$VT_LIB_DIR -lVT $VT_ADD_LIBS -o ftest
```

On Microsoft\* Windows\* you do not need to specify %VT\_ADD\_LIBS% because the corresponding libraries are automatically pulled in by the VT library:

```
mpiicc ctest.obj /link /LIBPATH:%VT_LIB_DIR% VT.lib
mpiifort ftest.obj /link /LIBPATH:%VT_LIB_DIR% VT.lib
```

If your MPI installation is different, then the command may differ and/or you might have to add further libraries manually. Usually it is important that the ITC library is listed on the command line in front of the MPI libraries: ...-lVT -lmpi.... In general, the same ITC library and link line is suitable for all compilers and programming languages.

Dependent on the platform \$VT\_ADD\_LIBS expands to the following

<b>em64t-lin-mpi3:</b>	-ldwarf -lelf -lvtunwind -lnsl -lm -ldl -lpthread
<b>em64t-lin-mpich:</b>	-ldwarf -lelf -lvtunwind -lnsl -lm -ldl -lpthread
<b>em64t-win-mpi32:</b>	ws32_2.lib
<b>em64t-win-mpi64:</b>	ws32_2.lib
<b>ia32-lin-mpi3:</b>	-ldwarf -lelf -lvtunwind -lnsl -lm -ldl -lpthread
<b>ia32-lin-mpich:</b>	-ldwarf -lelf -lvtunwind -lnsl -lm -ldl -lpthread
<b>ia64-lin-mpi3:</b>	-ldwarf -lelf -lvtunwind -lnsl -lm -ldl -lpthread
<b>ia64-lin-mpich:</b>	-ldwarf -lelf -lvtunwind -lnsl -lm -ldl -lpthread
<b>ia64-lin-mpt:</b>	-ldwarf -lelf -lvtunwind -lnsl -lm -ldl -lpthread

**Note:** For more convenient usage and extended portability it is recommended to use \$VT\_ADD\_LIBS rather than the expanded list of libraries.

**Note:** When using Intel® compilers, avoid explicitly linking against the math library. In this case, for better performance, it is recommended to *not* specify '-lm' and let the Intel® compiler use its own and more faster implementation.

One exception from these rules are C++ applications. If they call the C MPI API, then tracing works as described above, but if they use the MPI 2.0 C++ API, then ITC cannot intercept the MPI calls. They have to be mapped to the C function calls first with the help of a MPI implementation specific library which has to be placed in front of the ITC library. The name of that wrapper library depends on the MPI implementation; here is the command line option which needs to be added for some of them:

**Intel® MPI Library and Intel® C++ Compiler version 7.1** -lmpiec

**Intel® MPI Library and Intel® C++ Compiler version  $\geq 8.0$**  -lmpiic

**Intel® MPI Library and gcc < 3.0** -lmpigc

**Intel® MPI Library and gcc  $\geq 3.0$  and < 3.4** -lmpigc3

**Intel® MPI Library and gcc  $\geq 3.4$**  -lmpigc4

**MPICH\* 1.2.x** -lmpich++



### 3.1. TRACING MPI APPLICATIONS

---

Another exception are Fortran compilers which are incompatible with the Intel® Fortran Compiler that is used for compiling parts of libVT.a. The only system where such an incompatibility has been observed so far is the SGI Altix, where a segmentation fault occurs inside the MPT MPI startup code if Fortran code compiled with ifort is added to a Fortran binary which is linked with g77. As a workaround for this problem the relevant code is also provided as a library compiled with g77. It needs to be added to the link line like this:

```
mpif77 ftest.o -lVTg77 $VT_ADD_LIBS -o ftest
```

In all cases, the binary interface of the MPI libraries has to match the one used by ITC (see section 1.2 for details).

#### 3.1.3 Running MPI Programs with ITC

MPI programs linked with ITC as described in the previous sections can be started in the same way as conventional MPI applications. ITC reads two environment variables to access the values of runtime options:

**VT\_CONFIG** contains the pathname of an ITC configuration file to be read at MPI initialization time. A relative path is interpreted starting from the working directory of the MPI process specified with **VT\_CONFIG\_RANK**.

**VT\_CONFIG\_RANK** contains the rank (in MPI\_COMM\_WORLD) of the MPI process that reads the ITC configuration file. The default value is 0. Setting a different value has no effects unless the MPI processes do not share the same file system.

The trace data is stored in memory during the program execution, and written to disk at MPI finalization time. The name of the resulting tracefile depends on the format: the base name `<trace>` is the same as the path name of the executable image, unless a different name has been specified in the configuration file. Then different suffices are used depending on the file format:

**Structured Trace Format (STF, the default)** `<trace>.stf`

**single-file STF format** `<trace>.single.stf`

**old-style ASCII Vampir format** `<trace>.avt`

A directive in the configuration file (see section Configuration File Format) can influence which MPI process actually writes the tracefile; by default, it is the same MPI process that reads the configuration file.

If relative path names are used it can be hard to find out where exactly the tracefile was written. Therefore ITC prints an informational message to stderr with the file name and the current working directory as soon as writing starts.

#### 3.1.4 Examples

The examples in the `./examples` directory show how to instrument C and Fortran code to collect information about application subroutines. They come with a GNUmakefile (on Linux\*) or Visual Studio\* project files (on Microsoft\* Windows\*) that work for the MPI this ITC package was compiled for. If you use a different MPI, then you might have to edit this GNUmakefile. Unless ITC was installed in a private directory, the examples directory needs to be copied because compiling and running the examples requires write permissions.

### 3.1.5 Trouble Shooting

If generating a trace fails, check first that you can run MPI applications that were linked without ITC. Then ensure that your MPI is indeed compatible with the one this package was compiled for, as described under section 1.2. The FAQ may have further information. If this still does not help, then please submit a report via the Question and Answer Database (QuAD).

### 3.1.6 Handling of Communicator Names

By default ITC stores names for well-known communicators in the trace: “COMM\_WORLD”, “COMM\_SELF\_#0”, “COMM\_SELF\_#1”, ... When new communicators are created, their names are composed of a prefix, a space and the name of the old communicator. For example, calling `MPI_Comm_dup()` on `MPI_COMM_WORLD` will lead to a communicator called “DUP COMM\_WORLD”.

MPI Function	Prefix
<code>MPI_Comm_create()</code>	CREATE
<code>MPI_Comm_dup()</code>	DUP
<code>MPI_Comm_split()</code>	SPLIT
<code>MPI_Cart_sub()</code>	CART_SUB
<code>MPI_Cart_create()</code>	CART_CREATE
<code>MPI_Graph_create()</code>	GRAPH_CREATE
<code>MPI_Intercomm_merge()</code>	MERGE

`MPI_Intercomm_merge()` is special because the new communicator is derived from two communicators, not just one as in the other functions. The name of the new inter-communicator will be “MERGE <old name 1>/<old name 2>” if the two existing names are different, otherwise it will be just “MERGE <old name>”.

In addition to these automatically generated names ITC also intercepts `MPI_Comm_set_name()` and then uses the name provided by the application. Only the last name set with this function is stored in the trace for each communicator. Derived communicators always use the name which is currently set in the old communicator when the new communicator is created.

ITC does not attempt to synchronize the names set for the same communicator in different processes, therefore the application has to set the same name in all processes to ensure that this name is really used by ITC.

### 3.1.7 Tracing of Failing MPI Applications

Normally if a MPI application fails or is aborted, all trace data collected so far is lost: libVT needs a working MPI to write the trace file, but the MPI standard does not guarantee that MPI is still operational after a failure. In practice most MPI implementations just abort the application.

To solve this problem, link the application against libVTfs instead of libVT, like this:

```
mpicc ctest.o -lVTfs $VT_ADD_LIBS -o ctest
```

resp. on Microsoft\* Windows\*

```
mpicc ctest.obj VTfs.lib /OUT:ctest
```





### 3.1. TRACING MPI APPLICATIONS

---

Under normal circumstances tracing works just like with libVT, but communication during trace file writing is done via TCP sockets, so it may be a bit slower than over MPI. In order to establish communication, it needs to know the IP addresses of all involved hosts. It finds them by looking up the hostname locally on each machine or, if that only yields the 127.0.0.1 localhost IP address, falls back to broadcasting hostnames. In the latter case hostname lookup must work consistently in the cluster.

In case of a failure, libVTfs freezes all MPI processes and then writes a trace file with all trace data. Failures that it can catch include:

**Signals** These include events inside the applications like segfaults and floating point errors, but also abort signals sent from outside, like SIGINT or SIGTERM. Only SIGKILL will abort the application without writing a trace because it cannot be caught.

**Premature Exit** One or more processes exit without calling MPI\_Finalize().

**MPI Errors** MPI detects certain errors itself, like communication problems or invalid parameters for MPI functions.

**Deadlocks** If ITC observes no progress for a certain amount of time in any process, then it assumes that a deadlock has occurred, stops the application and writes a trace file. The timeout is configurable with [DEADLOCK-TIMEOUT](#). “No progress” is defined as “inside the same MPI call”.

Obviously this is just a heuristic and may fail to lead to both false positives and false negatives:

**Undetected Deadlock** If the application polls for a message that cannot arrive with MPI\_Test() or a similar, non-blocking function then ITC still believes that progress is made and will not stop the application. To avoid this the application has to use blocking MPI calls instead, which is also better for performance.

**Premature Abort** If all processes remain in MPI for a long time due to a long data transfer for instance, then the timeout might be reached. Because the default timeout is 5 minutes, this is very unlikely.

After writing the trace libVTfs will try to clean up the MPI application run by sending all processes in the same process group an INT signal. This is necessary because certain versions of MPICH\* may have spawned child processes which keep running when an application aborts prematurely, but there is a certain risk that the invoking shell also receives this signal and also terminates. If that happens, then it helps to invoke mpirun inside a remote shell:

```
rsh localhost 'sh -c "mpirun ..."'
```

MPI errors cannot be ignored by installing an error handler. libVTfs overrides all requests to install one and uses its own handler instead. This handler stops the application and writes a trace without trying to proceed, otherwise it would be impossible to guarantee that any trace will be written at all.

On Microsoft\* Windows\* not all features of POSIX\* signal handling are available. Therefore, VTfs on Microsoft\* Windows\* uses some heuristics and may not work as reliably as on Linux\*. Currently it is not possible to stop a Microsoft\* Windows\* application run and get a trace file by sending a signal or terminating the job in the Microsoft\* Windows\* task manager.

#### 3.1.8 Tracing MPI File IO

On Linux\* (only) Intel® Trace Collector for MPICH\* (and compatible) supports tracing of ROMIO, a portable implementation of MPI-IO. Fully standard-compliant implementations of MPI-IO are

untested, but might work. For SGI's MPT (Altix) tracing of ROMIO is only supported if the application avoids ROMIO's non-standard request handles.

This distinction is necessary because ROMIO normally uses its own request handles (MPIO\_Request) for functions like MPI\_File\_iread() and expects the application to call MPIO\_Wait()/MPIO\_Test(). These two functions are supported if and only if ITC is compiled with ROMIO support. In that case the wrapper functions for MPI\_File\_iread() are compiled for MPIO\_Requests and might not work if the MPI and the application use the normal MPI-2 MPI\_Request.

Applications which avoid the non-blocking IO calls should work either way.

### 3.1.9 Tracing MPI One-Sided Communication

On SGI Altix (MPT) Intel® Trace Collector supports tracing a commonly used subset of the one-sided communication calls in MPI. Nothing needs to be done to enable this tracing, linking as described in 3.1.2 is sufficient. This table lists which functions are traced and which information is recorded:

Information	Functions
function entry and exit	MPI_Win_create() MPI_Win_free() MPI_Win_fence() MPI_Win_lock() MPI_Win_unlock()
function entry and exit, message with same duration as function and size giving the amount of transferred bytes	MPI_Put() MPI_Get() MPI_Accumulate()

## 3.2 Tracing shmem Programs with ITC

On Silicon Graphics\* Itanium based systems with MPT\* Intel® Trace Collector supports tracing of SHMEM. SHMEM calls are also available through the Quadrics MPI implementation. The latter comes with the necessary instrumentation hooks inside the SHMEM library while MPT's SHMEM functions are intercepted by the Trace Collector.

Tracing programs that use SHMEM calls is very similar to tracing MPI programs. There is no need to change the source code of the program, relinking it with the ITC library is sufficient:

```
mpicc cshmem.o -lVT $VT_ADD_LIBS -lshmem -o cshmem
mpif77 fshmem.o -lVT $VT_ADD_LIBS -lshmem -o fshmem
```

ITC uses MPI calls internally, so linking requires the same libraries as in section 3.1.2 and the comments there about choosing the correct MPI still apply. Generating a trace also works as described above.

There are a few caveats:

**program name** If an unmodified SHMEM program is traced, ITC will initialize itself and MPI when shmem\_init() (Quadrics) or start\_pes (MPT) is called. Inside this call ITC has no access to the program's arguments and in C there is no global variable or function to obtain this



### 3.2. TRACING SHMEM PROGRAMS WITH ITC

information, therefore the program name will be set to “UNKNOWN”. By default, the tracefile will be called “UNKNOWN.stf”. PC tracing (section 3.8) would not work because it needs access to the binary. There are several solutions:

- In Fortran, ITC can use global functions to obtain the program name and the user does not need to do anything.
- In C, The application can be changed so that it calls either `VT_initialize()` or `MPI_Init()` before `shmem_init()` (Quadrics) or `start_pes` (MPT), which will set the program name based on the arguments supplied to these functions.
- The environment variable `VT_PROGNAME` or the configuration file setting `PROG-NAME` can be used to pass the executable file name to ITC without changing the source code (see `VT_CONFIG` for details).

**dynamic linking** ITC replaces the shmem functions and calls the original implementation using the dynamic library loader. This means that statically linking the shmem library is not possible and that a shared version is required. This is not a problem because the shared shmem library is the default anyway.

ITC supports the following shmem functions (Fortran functions in uppercase, C in lowercase) and records the information listed in this table:

Feature	Description
Information	Functions
start of program	SHMEM_INIT start_pes shmem_init START_PES
function entry and exit	SHMEM_MY_PE _my_pe SHMEM_N_PES SHMEM_QUIET SHMEM_WAIT shmem_my_pe _n_pes shmem_n_pes shmem_quiet shmem_wait
collective operation, function entry and exit	SHMEM_BARRIER SHMEM_BARRIER_ALL SHMEM_BROADCAST SHMEM_BROADCAST4 SHMEM_BROADCAST8 SHMEM_INT4_MAX_TO_ALL SHMEM_INT4_MIN_TO_ALL SHMEM_INT4_OR_TO_ALL SHMEM_INT4_PROD_TO_ALL SHMEM_INT4_SUM_TO_ALL SHMEM_INT4_XOR_TO_ALL SHMEM_REAL4_MAX_TO_ALL SHMEM_REAL4_MIN_TO_ALL SHMEM_REAL4_PROD_TO_ALL SHMEM_REAL4_SUM_TO_ALL shmem_double_max_to_all shmem_double_min_to_all shmem_double_prod_to_all shmem_double_sum_to_all shmem_longdouble_max_to_all shmem_longdouble_min_to_all shmem_barrier shmem_barrier_all shmem_broadcast shmem_broadcast32 shmem_broadcast64 SHMEM_INT8_MAX_TO_ALL SHMEM_INT8_MIN_TO_ALL SHMEM_INT8_OR_TO_ALL SHMEM_INT8_PROD_TO_ALL SHMEM_INT8_SUM_TO_ALL SHMEM_INT8_XOR_TO_ALL SHMEM_REAL8_MAX_TO_ALL SHMEM_REAL8_MIN_TO_ALL SHMEM_REAL8_PROD_TO_ALL SHMEM_REAL8_SUM_TO_ALL shmem_float_max_to_all shmem_float_min_to_all shmem_float_prod_to_all shmem_float_sum_to_all



Feature	Description
	shmem_longdouble_prod_to_all shmem_longdouble_sum_to_all shmem_short_and_to_all      shmem_int_and_to_all shmem_short_max_to_all      shmem_int_max_to_all shmem_short_min_to_all      shmem_int_min_to_all shmem_short_or_to_all      shmem_int_or_to_all shmem_short_prod_to_all      shmem_int_prod_to_all shmem_short_sum_to_all      shmem_int_sum_to_all shmem_short_xor_to_all      shmem_int_xor_to_all shmem_long_and_to_all      shmem_longlong_and_to_all shmem_long_max_to_all      shmem_longlong_max_to_all shmem_long_min_to_all      shmem_longlong_min_to_all shmem_long_or_to_all      shmem_longlong_or_to_all shmem_long_prod_to_all      shmem_longlong_prod_to_all shmem_long_sum_to_all      shmem_longlong_sum_to_all shmem_long_xor_to_all      shmem_longlong_xor_to_all
single message, function entry and exit	SHMEM_CHARACTER_GET      SHMEM_CHARACTER_PUT SHMEM_DOUBLE_GET      SHMEM_DOUBLE_PUT SHMEM_DOUBLE_IGET      SHMEM_DOUBLE_IPUT SHMEM_INTEGER_GET      SHMEM_INTEGER_PUT SHMEM_INTEGER_IGET      SHMEM_INTEGER_IPUT SHMEM_GET      SHMEM_PUT SHMEM_GET32      SHMEM_PUT32 SHMEM_GET64      SHMEM_PUT64 SHMEM_GET128      SHMEM_PUT128 SHMEM_GET4      SHMEM_PUT4 SHMEM_GET8      SHMEM_PUT8 SHMEM_IGET      SHMEM_IPUT SHMEM_IGET32      SHMEM_IPUT32 SHMEM_IGET64      SHMEM_IPUT64 SHMEM_IGET128      SHMEM_IPUT128 SHMEM_IGET4      SHMEM_IPUT4 SHMEM_IGET8      SHMEM_IPUT8 SHMEM_IXGET      SHMEM_IXPUT SHMEM_IXGET4      SHMEM_IXPUT4 SHMEM_REAL_GET      SHMEM_REAL_PUT SHMEM_REAL_IGET      SHMEM_REAL_IPUT shmem_double_get      shmem_double_put shmem_double_iget      shmem_double_iput shmem_float_get      shmem_float_put shmem_float_iget      shmem_float_iput shmem_get      shmem_put shmem_get32      shmem_put32 shmem_get64      shmem_put64 shmem_get128      shmem_put128 shmem_getmem      shmem_putmem shmem_iget      shmem_iput shmem_iget32      shmem_iput32



### 3.3. SINGLE-PROCESS TRACING

Feature	Description
	shmem_iget64            shmem_iput64 shmem_iget128        shmem_iput128 shmem_int_get         shmem_int_put shmem_int_iget        shmem_int_iput shmem_ixget            shmem_ixput shmem_ixget32         shmem_ixput32 shmem_long_get        shmem_long_put shmem_long_iget       shmem_long_iput shmem_longdouble_get shmem_longdouble_put shmem_longdouble_iget shmem_longdouble_iput shmem_longlong_get   shmem_longlong_put shmem_longlong_iget shmem_longlong_iput shmem_short_get      shmem_short_put shmem_short_iget     shmem_short_iput  shmem_double_g        shmem_double_p shmem_float_g         shmem_float_p shmem_int_g            shmem_int_p shmem_long_g          shmem_long_p shmem_short_g         shmem_short_p
pairwise message exchange, function entry and exit	SHMEM_INT4_SWAP      SHMEM_INT8_SWAP SHMEM_REAL4_SWAP    SHMEM_REAL8_SWAP SHMEM_SWAP shmem_double_swap    shmem_float_swap shmem_int_swap        shmem_long_swap shmem_longlong_swap shmem_short_swap shmem_swap  SHMEM_INT4_FADD      SHMEM_INT8_FADD shmem_int_fadd        shmem_long_fadd shmem_longlong_fadd shmem_short_fadd

Different tags are used for messages associated with shmem function calls. This can be used to filter for specific messages:

Function Call	Value of Tag
Put	100000
Get	100001
Swap	100002
Add	100003

### 3.3 Single-process Tracing

Traces of just one process can be generated with the libVTcs library, which allows the generation of executables that work without MPI.

Linking is accomplished by adding libVTcs.a (resp. VTcs.lib on Microsoft\* Windows\*) and the libraries it needs to the link line:

```
-lVTcs $VT_ADD_LIBS
```

The application has to call `VT_initialize()` and `VT_finalize()` to generate a trace. Additional calls exist in `libVTcs` to also trace distributed applications, that is why it is called “client-server”. Tracing a single process is just a special case of that mode of operation. Tracing distributed applications is described in more detail in section 6.

Subroutine tracing (3.4) or binary instrumentation (3.4.4) can be used with and without further ITC API (see chapter 8) calls to actually generate trace events.

`libVTcs` uses the same techniques as fail-safe MPI tracing (3.1.7) to handle failures inside the application, therefore it will generate a trace even if the application segfaults or is aborted with CTRL-C.

## 3.4 Compiler-driven Subroutine Instrumentation

### 3.4.1 Intel® Compilers 10.0 and later

The Intel® compiler can automatically instrument functions during compilation. At runtime Trace collector will record all function entries and exits in those compilation units. Compile time instrumentation is enabled with the switch “-tcollect” (Linux\*) or “/Qtcollect” (Microsoft\* Windows\*). The switch accepts an optional argument to specify the collecting library to link against. For example, for non-MPI applications you can select “libVTcs” as follows: “-tcollect=VTcs”. The default value is “VT”.

Before using this switch with the Intel® compiler the Trace Collector must have been set up through one of its set-up scripts.

Note, that while for MPI applications the initialization is done automatically, manual interaction is needed for non-MPI programs. In this case you must ensure that the Trace Collector gets properly initialized through its API routines “`VT_initialize`” or “`VT_init`”.

### 3.4.2 gcc/g++

Similar function tracing is possible through the GNU\* compiler suite version 2.95.2 or later. Object files that contain functions to be traced are compiled with “-finstrument-function” and VT should be able to obtain output about functions in the executable. By default this is done by starting the shell program “`nm -P`”, which can be changed with the `NMCMDB` config option.

### 3.4.3 Folding

Function tracing can easily generate large amounts of trace data, especially for object oriented programs. Folding function calls at run-time can help here, as described in section 3.13.

### 3.4.4 C++ name demangling

By default Trace Collector records function names in their mangled form. The configuration option `DEMANGLE` allows to enable automatic demangling of C++ names.



## 3.5 Tracing of Binaries and Binary Instrumentation

### Synopsis

```
itcpin [<ITC options>] -- <application command line>
      <ITC options> - described below
      <command line> - command and (when running it) its options
```

### Description

The itcpin utility program manipulates a binary executable file while it runs. It can:

- insert an ITC library into the binary as if the executable had been linked against it
- automatically initialize the ITC library, if necessary
- record function entry and exit events, thus allowing more detailed analysis of the user code in an application

### Analysis

Without further options itcpin will just analyze the executable given on the command line to ensure that it can be instrumented and how. With the `--list` option it will print a list of all functions found inside the executable to stdout. The format of this list is the same as the one used for the STATE configuration option and its ON/OFF flag indicates whether tracing of a function would be enabled or not. `--list` can be combined with options that specify a configuration to test their effect without actually running the executable. One relevant options is `--debug`, which groups functions by the source file that contains them. The top-level group is always the binary file containing the function, leading to function names of the format: `<basename binary file>:<basename source file>:<function name>`

C++ names are demangled automatically if `--demangle` is specified. In this case their methods are grouped according to the class hierarchy by default instead of using the normal file oriented grouping. When `--filter` is used, then the filter script is passed all available information and can decide itself which grouping it wants to use.

Note that the function list generated that way is limited to the main executable and those dynamic libraries which are already loaded during startup. Functions in libraries which are opened dynamically during the normal execution of the application will not be found this way.

### Running

The executable is run only if the `--run` option is given. Unless instructed otherwise, itcpin will insert libVT if it finds that the main executable references MPI calls. In all other cases it is necessary to choose which library to insert with the `--insert` option.

The installation path of the Trace Collector must be the same on all nodes (see section 'Installation') to ensure that it can find the necessary binaries at run-time.

Invoking itcpin on the executable as described in the previous section will print a list of all available libraries with a short description of each one. The ITC documentation also has a full list of all available libraries in the "System Requirements and Supported Features" section. libVTcs is the one used for ordinary function tracing.

If you want to do MPI tracing and MPI was linked statically into the binary, then it is necessary to point itcpin towards a shared version of a matching MPI library with `--mpi`.

Choosing which tracing library to insert and the right MPI library is useful, but not required when just using `--list`: if given, then itcpin will hide functions that are internal to those libraries and thus cannot be traced.

## Function Tracing

The optional function profiling is enabled with the "--profile" flag. This records the entry and exit for functions in the trace file. Limiting the number of recorded functions is recommended to avoid excessive runtime overhead and reduce the amount of trace data. This can be done with one or more of the following options: "--state", "--activity", "--symbol", "--config". Alternatively, you can use "folding" to prune the amount of recorded trace data dynamically at runtime; see the section "Tracing Library Calls" in the ITC documentation for details.

## Initialization

ITC libraries must be initialized before they can be used. In MPI tracing libraries this is done implicitly when MPI.Init() is called, so inserting the library is enough.

For the other libraries there are two possibilities:

- The application may contain calls to `VT_initialize()` and (for libVTcs) `VT_clientinit()/VT_serverinit()`. To get the application linked libVTnull can be used. During binary instrumentation all API calls will be redirected into the actual ITC library. This is also useful when tracing MPI applications, for example to store additional data in the trace file.
- If the application contains no call to `VT_initialize()`, then itcpin will call `VT_initialize()` as soon as the ITC library gets inserted.

## Startup Scripts

It is quite common that MPI applications are started via scripts. It is possible to invoke itcpin on the startup script or program loader. itcpin will then monitor this initial loader and all commands started by it until it finds the main executable.

When inserting an MPI tracing library (regardless whether it was selected explicitly via "--insert" or not) then the first executable which contains MPI calls is treated as the main executable. If the main executable contains no MPI calls because all of them were moved to a shared library which is only going to be loaded later, then this heuristic fails.

In that case and when inserting other ITC libraries, the "--executable" command line option can be used to specify which executable is to be instrumented.

## Limitations

The Microsoft\* Windows\* version of itcpin has some limitations against Linux\* one.

Unless the binary to be instrumented comes with a .pdb symbol file (i.e. has been built with debug information), itcpin does not see the symbols inside the main binary and thus cannot detect whether it is an MPI application. In this situation the user has to specify explicitly which ITC library should be inserted (via --insert).

There is another difference to Linux\*: the name of the MPI dll the application is linked to has to be specified, either via --mpi or via the environment variable `VT_MPI_DLL`. The latter is already done in the itacvars script, therefore no special action is needed if the application is linked to the standard MPI dll and itacvars has been executed. When running under itcpin, it is important that the environment variables `VT_DLL_DIR` and `VT_MPI_DLL` are set on all MPI processes. Depending on your MPI, this might require special flags for mpiexec (e.g. mpiexec -env). For Intel(R) MPI, as an example, after executing the mpivars and itacvars scripts, the startup command might look like

```
mpiexec -hosts ... -wdir ... -genv VT_DLL_DIR "%VT_DLL_DIR%"
-genv VT_MPI_DLL "%VT_MPI_DLL%" itcpin --run -- my_app.exe
```





### 3.5. TRACING OF BINARIES AND BINARY INSTRUMENTATION

---

To use itcpin on Microsoft\* Windows\* you have to disable the "McAfee Host Intrusion Prevention"\* antivirus software.

#### Supported Directives

##### --run

**Syntax:**

**Default:** off

itcpin only runs the given executable if this option is used. Otherwise it just analyzes the executable and prints configurable information about it.

##### --use-debug

**Syntax:**

**Default:** on

Can be used to disable the usage of debugging information for building the function names in the trace file. By default debugging information is used to find the source file of each function and to group those functions together in the same class.

##### --list

**Syntax:**

**Default:** off

Enables printing of all functions found inside the input executable and their tracing state. Function names are listed as they would appear in the trace file:

- class(es) and basic function name are separated by colon(s)
- C++ function names are demangled and the C++ class hierarchy is used if "--demangle" is specified; function parameters are stripped to keep the function names shorter
- functions without such a class or namespace are grouped by source file if that debug information is available; only the basename of the source file is used (foo.c:bar)
- all other functions are inside the "Application" default class

##### --filter

**Syntax:** <pattern> <replacement>

This option allows to transform function names that are encountered in the binary file during execution into more useful names that will appear as predefined functions and function groups in the trace file. For example, all functions with a common prefix FOO\_ (FOO\_bar) could be turned into functions inside a common group FOO (FOO:bar).

Please note that this option has changed significantly compared to itcinstrument that was available in earlier versions of the Trace Collector.

The arguments consist of a pattern that is matched against the input and a replacement expression that controls the transformation into the output.

The input function names have nearly the same format as in the --list output above. They contain slightly more information so that a filter can flexibly reduce that information:

- source file names contain the full path, if available
- C++ functions also have their source file as top level class

Example input:

- /home/joe/src/foo.c:FOO\_bar
- Application:FOO\_bar
- /home/joe/src/foo.cpp:app:foo:bar

Passing --filter 'Application:FOO\_(.\*)' 'FOO:\$1' would transform "Application:FOO\_bar" into "FOO:bar". The special expression \$1 in the replacement pattern refers to the part of the input that was matched by the first parenthesis in the pattern expression. Note that the single quotes are only needed to protect the expressions from being garbled by the shell, they are not part of the expression. If the pattern or the replacement string contain characters like \$ or () which are treated specially by the shell it is recommended to specify the filter expression via an ITC config file: this file would contain lines like

FILTER 'Application:FOO\_(.\*)' 'FOO:\$1'

and would be defined to itcpin via `--config`.

You can specify several `--filter` options that are applied from left to right. Lets try to strip the common prefix `/home/joe/` from the input and then use the remaining directory and file names as groups.

First we throw away the common prefix: `--filter '/home/joe/(.*)' '$1'`

Then we convert slashes to colons: `--filter '/' ':'`

As another example you might want to handle Fortran 90 module functions by stripping the source file or class, then converting the underscore in the function name into a class separator `--filter '^([^\:]*:([^\_]*_){2,})$' '$1' --filter '_' ':'` This works for example, for `src/foo.f90:foo_bar_`.

While the syntax for the pattern expression and the replacement expression is very similar to the Perl language the underlying regex library is taken from the boost library project (<http://www.boost.org/>), regex version 1.34.1. Note that `--filter` replaces all matched patterns with the replacement, while Perl replaces only the first match by default.

For a detailed reference of the regular expression syntax in the `<pattern>` argument please refer to ['http://www.boost.org/libs/regex/doc/syntax\\_perl.html'](http://www.boost.org/libs/regex/doc/syntax_perl.html), For a detailed reference of the special expressions usable in the `<replacement>` argument (named "Format String" in boost terms) refer to ['http://www.boost.org/libs/regex/doc/format\\_perl\\_syntax.html'](http://www.boost.org/libs/regex/doc/format_perl_syntax.html).

#### `--insert`

**Syntax:** `<libname>`

**Default:** `libVT` for MPI applications

ITC has several libraries that can be used to do different kinds of tracing. For MPI applications the most useful one is `libVT`, so it is the default. For other applications `itcpin` cannot guess what the user wants to do, so the library which is to be inserted needs to be specified explicitly.

#### `--mpi`

**Syntax:** `<path to MPI>`

If an MPI application is linked statically against MPI, then its executable only contains some of the MPI functions. Several of the functions required by `libVT` may not be present. In this case running the instrumented binary will fail with link errors. `itcpin` tries to detect this failure, but if it happens it will not be able to guess what the MPI is that the application was linked against.

This option provides that information. The MPI installation must have shared libraries which will be searched for in the following places, in this order:

- `<path>`
- `<path>/lib`
- `<path>/lib/shared` and the names (first with version 1.0, then without):
- `libmpich.so`
- `libmpich.so`
- `libmpi.so`
- `libmpi.so`

If `<path>` points towards a file, that file has to be a shared library which implements the PMPI interface and is used directly.

#### `--profile`

**Syntax:**

**Default:** `off`

Enables function profiling in the instrumented binary. Once enabled, all functions in the executable will be traced. It is recommended to control this to restrict the runtime overhead and the amount of trace data by disabling functions which do not need to be traced (see `--state/symbol/activity` filters).



#### **--config**

**Syntax:** <filename>

Specifies a ITC configuration file with STATE, ACTIVITY, SYMBOL configuration options. The syntax of these options is explained in more detail in the documentation of [VT\\_CONFIG](#) and the normal pattern matching rules apply.

In this context it only matters whether tracing of a specific function is ON or OFF. Rule entries given on the command line with **--state**, **--activity**, **--symbol** are evaluated before entries in the configuration file.

#### **--executable**

**Syntax:** <file pattern>

Specifies the executable into which the ITC library is to be inserted. When analyzing MPI applications, the default is to pick the first executable which contains MPI calls. Otherwise the first executable invoked by the command line will be instrumented.

The parameter is a file pattern which must match a substring of the full executable name. With | multiple different file patterns can be separated. Note that the real name of the executable file is matched against and not the name of a symbolic link via which it might have been invoked.

To find out which executables itcpin looks at and why it ignores the "right" one, run with verbosity level 3.

#### **--max-threads**

**Syntax:** <number>

**Default:** 100

One internal data structure which tracks threads must have a fixed size to avoid locking. This parameter determines the size of that structure. It must be larger than the number of threads created during the application run and only has to be increased if the run aborts with an error message that instructs to do so.

#### **--verbose**

**Syntax:** [on|off|<level>]

**Default:** on

Enables or disables additional output on stderr. <level> is a positive number, with larger numbers enabling more output:

- 0 (= off) disables all output
- 1 (= on) enables only one final message about generating the result
- 2 enables general progress reports by the main process
- 3 enables detailed progress reports by the main process
- 4 the same, but for all processes (if multiple processes are used at all)

Levels larger than 2 may contain output that only makes sense to the developers of ITC.

#### **--state**

**Syntax:** <pattern> <filter body>

**Default:** on

Defines a filter for any state or function that matches the pattern. Patterns are extended shell patterns: they may contain the wild-card characters \*, \*\*, ? and [] to match any number of characters but not the colon, any number of characters including the colon, exactly one character or a list of specific characters. Pattern matching is case insensitive.

The state or function name that the pattern is applied to consists of a class name and the symbol name, separated by a : (colon). Deeper class hierarchies as in Java or C++ may have several class names, also separated by a colon. The colon is special and not matched by the \* or ? wildcard. To match it use \*\*. The body of the filter may specify the logging state with the same options as [PCTRACE](#). On some platforms further options are supported, as described below.

Valid patterns are:

- MPI:\* (all MPI functions)
- java:util:Vector:\* (all functions contained in Vector classes)
- \*:\*send\* (any function that contains "send" inside any class)

- `**:*send*` (any function that contains "send", even if the class actually consists of multiple levels; same as `**send*`)
- `MPI:*send*` (only send functions in MPI)

**--symbol**

**Syntax:** <pattern> <filter body>

**Default:** on

A shortcut for STATE `"**:<pattern>".`

**--activity**

**Syntax:** <pattern> <filter body>

**Default:** on

A shortcut for STATE `"<pattern>:*".`

## 3.6 Multithreaded Tracing

To trace multithreaded applications, just link and run as described above. Additional threads will be registered automatically as soon as they call ITC via MPI wrapper functions or the API. Within each process every thread will have a unique number starting with zero for the master thread.

With the `VT_registerthread()` API function the application developer can control how threads are enumerated. `VT_registernamed()` also supports recording a thread name. `VT_getthrank()` can be used to obtain the thread number that was assigned to a thread.

## 3.7 Recording Statistical Information

ITC is able to gather and store statistics about the function calls and their communication

These statistics are gathered even if no trace data is collected, therefore it is a good starting point for trying to understand an unknown application that might produce an unmanageable trace. To run an application in this light weight mode you can either set the environment variables `VT_STATISTICS=ON` and `VT_PROCESS=OFF` or point with `VT_CONFIG` to a file like this:

```
# enable statistics gathering
STATISTICS ON

# no need to gather trace data
PROCESS 0:N OFF
```

The statistics are written into the STF file. The `stftool` (see section 7.4.1) can convert from the machine-readable format to ASCII text with `--print-statistics`.

The format was chosen so that text processing programs and scripts such as `awk`, `perl`, and `Excel` can read it. In one line each it prints for each tuple of

- Thread or process
- Function
- Receiver (if applicable)
- Message size (if applicable)
- number of involved processes (if applicable)



### 3.7. RECORDING STATISTICAL INFORMATION

---

the following statistics:

- Count; number of communications or number of calls as applicable
- Minimum execution time exclusive callee time
- Maximum execution time exclusive callee time
- Total execution time exclusive callee time
- Minimum execution time inclusive callee time
- Maximum execution time inclusive callee time
- Total execution time inclusive callee time

Within each line the fields are separated by colons (:).

Receiver is set to 0xffffffff for file operations and to 0xffffffe for collective operations. If message size equals 0xffffffff the only defined value is 0xffffffe to mark it a collective operation.

The message size is the number of bytes sent or received per single message. With collective operations the following values (buckets) (of message size) are used for individual instances:

	Process-local bucket	Is same value on all processes?
MPI_Barrier	0	Yes
MPI_Bcast	number of broadcasted bytes	Yes
MPI_Gather	number of bytes sent	Yes
MPI_Gatherv	number of bytes sent	No
MPI_Scatter	number of bytes received	Yes
MPI_Scatterv	number of bytes received	No
MPI_Allgather	number of bytes sent + received	Yes
MPI_Allgatherv	number of bytes sent + received	No
MPI_Alltoall	number of bytes sent + received	Yes
MPI_Alltoallv	number of bytes sent + received	No
MPI_Reduce	number of bytes sent	Yes
MPI_Allreduce	number of bytes sent + received	Yes
MPI_Reduce_Scatter	number of bytes sent + received	Yes
MPI_Scan	number of bytes sent + received	Yes

Message is set to 0xffffffff if no message was sent, e.g. for non-MPI functions or functions like MPI\_Comm\_rank.

If more than one communication event (message or collective operation) occur in the same function call (as it can happen for instance with MPI\_Waitall, MPI\_Waitany, MPI\_Testsome, MPI\_Sendrecv etc.), the time in that function is evenly distributed over all communications and counted once for each message or collective operation. This implies that it is impossible to compute a correct traditional function profile from the data referring to such function instances (e.g. those that are involved in more than one message per actual function call). Only the 'Total execution time inclusive callee time' and the 'Total execution time exclusive callee time' can be interpreted similar to the traditional function profile in all cases.

The number of involved processes is negative for received messages. If messages were received from a different process/thread it is -2.

Statistics are gathered on the thread level for all MPI functions and for all functions which were instrumented through the API (see section 8), binary instrumentation (see section 3.4.4) or compiler driven instrumentation (see section 3.4).

Filter utilities, such as `awk` and `perl`, and plotting/spreadsheet packages, like Excel, can process the statistical data easily. In the examples directory a perl script called `convert-stats` is provided that illustrates how the values printed by `stftool` (called with the `--dump` and `--print-statistics` options) might be processed: it extracts the total times and transposes the output so that each line has information about one function and all processes instead of one function and process as in the protocol file. It also summarizes the time for all processes. For messages the total message length is printed in a matrix with one row per sender and one column per receiver.

## 3.8 Recording Source Location Information

The Intel® Trace Collector can automatically record the locations of subroutine calls in the source code. Compile the relevant application modules with support for debugging by using these compiler flags that enable the generation of debug information for ITC:

```
mpicc -g -c ctest.c
mpif77 -g -c ftest.c
```

If your compiler does not support a flag, then search for a similar one.

At runtime, enable Program Counter (PC) tracing by either setting the environment variable `VT_PCTRACE` to 5 for example, or by setting `VT_CONFIG` to the name of a configuration file specifying e.g.:

```
# trace 4 call levels whenever MPI is used
ACTIVITY MPI 4

# trace one call level in all routines not mentioned
# explicitly; could also be for example, PCTRACE 5
PCTRACE ON
```

`PCTRACE` sets the number of call levels for all subroutines that do not have their own setting. Because unwinding the call stack each time a function is called can be very costly and cause considerable runtime overhead, `PCTRACE` is disabled by default and has to be handled with care. It is useful to get an initial understanding of an application which then is followed by a performance analysis without automatic source code locations.

Manual instrumentation of the source code with the ITC API can provide similar information but without the performance overhead (see `VT_scldef()`/`VT_thisloc()` in section 8.3 for more information).

### 3.8.1 Notes for IA32 and Intel®64

On ia32-Linux and Intel®64 the compiler generates dwarf-2 debug infos. This is supported by GCC and was even made the default in GCC 3.1, but older releases need `-gdwarf-2` to enable that format. The Intel® compiler also uses it by default since at least version 7.0 and does not need any special options.

Another requirement is that the compiler has to use normal stack frames. This is the default in GCC, but might have been disabled with `-fomit-frame-pointer`. If that flag is used, then only the direct caller of MPI or API functions can be found and asking ITC to unwind more than one stack level may lead to crashes. The Intel® compiler does *not* use normal stack frames by default if optimization is enabled, but it is possible to turn them on with `-fp`. As of version 10.0 of the



Intel® compiler, this option is deprecated, use `-fno-omit-frame-pointer` instead. Support by other compilers for both features is unknown.

## 3.9 Recording Hardware Performance Information

On Linux\* The Intel® Trace Collector can sample Operating System values for each process with the `getrusage()` system call and hardware counters with the Performance Application Programming Interface (PAPI). Because PAPI and `getrusage()` might not be available on a system, support for both is provided as an additional layer on top of the normal ITC.

This layer is implemented in the `VT_sample.c` source file. It was possible to provide a pre-compiled object files only for IA32 systems, because PAPI was either not available or not installed when this package was prepared. The `VT_sample.o` file can be rebuilt by entering the ITC lib directory, editing the provided Makefile to match the local setup and then typing “make `VT_sample.o`”. It is possible to compile `VT_sample.o` without PAPI by removing the line with `HAVE_PAPI` in the provided Makefile. This results in a `VT_sample.o` that only samples `getrusage()` counters, which is probably not as useful as PAPI support.

Add the `VT_sample.o` object file to the link line in front of the ITC library. With the symbolic link from `libVTsample.a` to `VT_sample.o` that is already set in the lib directory it is possible to use `-lVTsample` and the normal linker search rules to include this object file. If it includes PAPI support, then add `-lpapi` also, together with all libraries PAPI itself needs, for example `-lpfm` to find symbols from `libpfm`—please refer to the PAPI documentation for details, which also describes all other aspects of using PAPI. The link line might look like the following one:

```
mpicc ctest.o <search path for PAPI> -lVTsample -lVT -lpapi
    $VT_ADD_LIBS <libs required by PAPI> -o ctest
```

Run the application with configuration options that enable the counters of interest. Because ITC cannot tell which ones are interesting, all of them are disabled by default. The configuration option “**COUNTER** <counter name> ON” enables the counter and accepts wildcards, so that for example “**COUNTER** PAPI\_\* ON” enables all PAPI counters at once. Section 9 describes how to use configuration options.

However, enabling all counters at once is usually a bad idea because logging counters not required for the analysis just increases the amount of trace data. Even worse is that many PAPI implementations fail completely with an error in `PAPI_start_counters()` when too many counters are enabled because some of the selected counters are mutually exclusive due to restrictions in the underlying hardware (see PAPI and/or hardware documentation for details).

PAPI counters are sampled at runtime each time a function entry or exit is logged. If this is not sufficient f.i. because a function runs for a very long time, give ITC a chance to log data. This is done by inserting calls to `VT_wakeup()` into the source code.

The following Operating System counters are always available, but might not be filled with useful information if the operating system does not maintain them. They are not sampled as often as PAPI counters, because they are unlikely to change as often. ITC only looks at them if 0.1 seconds have passed since last sampling them. This delay is specified in the `VT_sample.c` source code and can be changed by recompiling it. Consult the man page of `getrusage()` or the system manual to learn more about these counters:

Counter Class: OS		
Counter Name	Unit	Comment
RU_ETIME	s	user time used
RU_STIME	s	system time used
RU_MAXRSS	bytes	maximum resident set size
RU_IXRSS	bytes	integral shared memory size
RU_IDRSS	bytes	integral unshared data size
RU_ISRSS	bytes	integral unshared stack size
RU_MINFLT	#	page reclaims—total vmfaults
RU_MAJFLT	#	page faults
RU_NSXAP	#	swaps
RU_INBLOCK	#	block input operations
RU_OUBLOCK	#	block output operations
RU_MSGSND	#	messages sent
RU_MSGRCV	#	messages received
RU_NSIGNALS	#	signals received
RU_NVCSW	#	voluntary context switches
RU_NIVCSW	#	involuntary context switches

The number of PAPI counters is even larger and not listed here. They depend on the version of PAPI and the CPU. A list of available counters including a short description is usually produced with the command:

```
<PAPI root>/ctests/avail -a
```

### 3.10 Recording OS Counters

Similar to the process specific counters in the previous section, ITC can also record some Operating System counters which provide information about a node. In contrast to the process specific counters these counters are sampled only very infrequently by one background thread per node and thus the overhead is very low. The amount of trace data also increases just a little.

Nevertheless recording them is turned off by default and needs to be enabled explicitly with the configuration option “**COUNTER** <counter name> ON”. The supported counters are:

Counter Class: OS		
Counter Name	Unit	Comment
disk_io	KB/s	read/write disk IO (any disk in the node)
net_io	KB/s	read/write network IO (any system interface) This might not include the MPI transport layer.
cpu_ ...	percent	average percentage of CPU time of all CPUs spent in ...
cpu_idle	percent	... idle mode
cpu_sys	percent	... system code
cpu_usr	percent	... user code

The delay between recording the current counter values can be changed with the configuration option “**OS-COUNTER-DELAY**”, with a default of one second. CPU utilization is calculated by the OS with sampling, therefore a smaller value does not necessarily provide more detailed information. Increasing it could reduce the overhead further, but only slightly because the overhead is hardly measurable already.

These OS counters appear in the trace as normal counters which apply to all processes running on a node.





## 3.11 Using the Dummy Libraries

Programs containing calls to the ITC API (see section 8) can be linked with a “dummy” version of the profiling libraries to create an executable that will not generate traces and incur a much smaller profiling overhead. This library is called `libVTnull.a` and resides in the ITC library directory. Here’s how a C MPI-application would be linked:

```
mpicc ctest.o -lVTnull $VT_ADD_LIBS -o ctest
```

## 3.12 Using the Shared Libraries

This version of the Intel® Trace Collector also provides all of its libraries as shared objects. Using the static libraries is easier to handle, but in some cases the shared libraries might be useful. They are located in the directory “`itac/slib_<mpi>`” (Linux\*) resp. “`dll\<mpi>`” (Microsoft\* Windows\*). After sourcing the `itacvars` script with the appropriate `<mpi>` argument, the path of the shared libraries’ directory is contained in the environment variable `VT_SLIB_DIR` (resp. `VT_DLL_DIR` on Microsoft\* Windows\*). It is recommended to use this variable in linker flags like `-L$(VT_SLIB_DIR)` in your Makefile.

To use the shared libraries on Linux\*, add `-L$(VT_SLIB_DIR)` to the command line of your linker. Then ensure that your `LD_LIBRARY_PATH` includes this directory *on all nodes* where the program is started. This can be done either by automatically sourcing the `itacvars` scripts in the login scripts of one’s account, setting the variable there directly, or by running the program inside a suitable wrapper script.

The installation path of the Intel® Trace Collector should be the same on all nodes (see section 2) to ensure that it can find the necessary binaries at run-time.

Two different bindings for Fortran are supported in the same library. This works fine when linking against the static ITC because the linker automatically picks just the required objects from the library. When using shared libraries, though, it will refuse to generate a binary because it finds unresolved symbols and cannot tell that those are not needed. To solve this, add `-Wl,--allow-shlib-undefined` to the link line. Note that in some distributions of Linux, f.i. RedHat Enterprise Linux 3.0, the linker’s support for this option is broken so that it has no effect (ld version 2.14.90.0.4).

Alternatively you can insert the ITC into a MPI binary that was not linked against it. For that to work MPI itself has to be linked dynamically. For MPICH\*, you need to configure MPICH\* with `--enable-sharedlib`, then link the application either with `-shlib` on the command line or the environment variable `MPICH_USE_SHLIB` set to “yes”. When running the dynamically linked MPI application, set `LD_LIBRARY_PATH` as described above and in addition to that, set the environment variable `LD_PRELOAD` to “`libVT.so:libpthread.so:libdl.so`”. Even more convenient is the simple use of the ‘`-trace`’ option which is provided by ‘`mpiexec`’ of Intel® MPI library.

To use the dll versions of ITC on Microsoft\* Windows\* you need a full ITC installation on each node. Executing the `itacvars` script with the appropriate MPI argument makes sure that the directory of the ITC dlls (`VT_DLL_DIR`) is added to the `PATH` so that they are found at runtime. On Microsoft\* Windows\*, the ITC dlls have a special feature: they are not directly linked against MPI, but load the MPI interface dynamically at runtime. Which MPI dlls are to be loaded by ITC is defined via environment variables `VT_MPI_DLL` resp. `VT_FMPI_DLL` for the C resp. Fortran MPI dll. These variables are set via the `itacvars` script to the default dll of the corresponding MPI (e.g. “`impi.dll`” for Intel® MPI), but may be changed to a different, but binary compatible MPI dll (e.g. “`impid.dll`”).

### 3.13 Tracing Library Calls

Suppose you have an application that makes heavy use of libraries or software components which might be developed independently of the application itself. As an application developer the relevant part of the trace are the events inside the application and the top-level calls into the libraries made by the application, but not events inside the libraries. As a library developer the interesting part of a trace are the events inside one's library and how the library functions were called by the application.




Figure 3.1: General structure of an application using many different libraries.

Figure 3.1 shows the calling dependencies in a hypothetical application. This is the application developer's view on improving performance:

- lib1, lib2, lib4 are called by the application; the application developer codes these calls and can change the sequence and parameters to them to improve performance (arrows marked as 1)
- lib3 is never directly called by the application. The application developer has no way to tailor the use of lib3. These calls (arrows marked as 3) are therefore of no interest to him, and detailed performance data is not necessary.
- lib4 is called both directly by the application, and indirectly through lib2. Only the direct use of lib4 can be influenced by the application developer, and the information about the indirect calls (arrows marked 4) are not interesting to her.

For the library developer, the performance analysis model is significantly different. Here, the workings of the application are of no concern apart perhaps from call paths that lead into the library. The library developer will need detailed information about the workings of say lib2, including the calls from the application, and the calls to component libraries (lib3 and lib4), and to system-level services (MPI). The library developer of lib2 will have no interest in performance data for lib1, and similarly the library developers of lib1 will have no interest in data from lib2, lib3, and lib4.

If the application and the involved libraries are instrumented to log function calls (either manually or with a compiler), then Intel(R) Trace Collector supports tracing of the application in a way that just the interesting data is recorded. This is done by writing a filter rule that turns off tracing



### 3.13. TRACING LIBRARY CALLS

once a certain function entry has been logged and turns it on again when the same function is left again. This effectively hides all events inside the function. In analogy to the same operation in a graphical tree view this is called *FOLDING* in Intel(R) Trace Collector. *UNFOLDING* is the corresponding operation that resumes tracing again in a section that otherwise would have been hidden. In contrast to turning tracing on and off with the API calls `VT_traceon()` and `VT_traceoff()`, folding does not log a pseudo-call to “VT\_API:TRACEOFF”. Otherwise folding a function that does not call any other function would log more, not less data. It is also not necessary to turn tracing on again explicitly, this is done automatically.

Folding is specified with the `STATE`, `SYMBOL` or `ACTIVITY` configuration options. Shell wildcards are used to select functions by matching against their name (`SYMBOL`), class (`ACTIVITY`) or both (`STATE`). “FOLD” and “UNFOLD” are keywords that trigger folding or unfolding when a matching function is entered. With the “CALLER” keyword one can specify as an additional criteria that the calling function match a pattern before either folding or unfolding is executed. Section 9.6 has a detailed description of the syntax.

In this section folding is illustrated by giving configurations that apply to the example given above. A C program is provided in `examples/libraries.c` that contains instrumentation calls that log a calltree as it might occur from a program run with library dependencies as in 3.1. Here is an example of call tree for the complete trace (calls were aggregated and sorted by name, therefore the order is not sequential):

```
\->User_Code
  +->finalize
  | \->lib2_end
  +->init
  | +->lib1_fini
  | \->lib1_main
  |   +->close
  |   +->lib1_util
  |   +->open
  |   \->read
  +->lib4_log
  | \->write
  \->work
    +->lib2_setup
    | +->lib3_get
    | | \->read
    | \->lib4_log
    |   \->write
    \->lib4_log
      \->write
```

By using the configuration options listed below, different parties can run the same instrumented executable to get different traces:

**application developer:** trace the application with only the top-level calls in lib1, lib2, and lib4

```
STATE lib*:* FOLD

\->User_Code
  +->finalize
  | \->lib2_end
  +->init
  | +->lib1_fini
```



```
| \->lib1_main
+-->lib4_log
\->work
  +-->lib2_setup
  \->lib4_log
```

**lib2 developer:** trace everything in lib2, plus just the top-level calls it makes

```
STATE ** FOLD
STATE lib2:* UNFOLD

\->User_Code
  +-->finalize
  | \->lib2_end
  \->work
    \->lib2_setup
      +-->lib3_get
      \->lib4_log
```

**lib2 developer, detailed view:** trace the top-level calls to lib2 and all lib2, lib3, lib4, and system services invoked by them

```
STATE Application:* FOLD
STATE lib2:* UNFOLD

\->User_Code
  +-->finalize
  | \->lib2_end
  \->work
    \->lib2_setup
      +-->lib3_get
      | \->read
      \->lib4_log
        \->write
```

**application and lib4 developers:** trace just the calls in lib4 issued by the application

```
STATE ** FOLD
STATE lib4:* UNFOLD CALLER Application:*

\->User_Code
  +-->lib4_log
  | \->write
  \->work
    \->lib4_log
      \->write
```

It is assumed that application, libraries and system calls are instrumented so that their classes are different. Alternatively you could match against a function name prefix that is shared by all library calls in the same library.

## Chapter 4

# Correctness Checking

### 4.1 Overview

The checking addresses two different concerns:

- Finding programming mistakes in the application which need to be fixed by the application developer. These include potential portability problems and violations of the MPI standard which do not immediately cause problems, but might when switching to different hardware or a different MPI implementation.
- Detecting errors in the execution environment. This is typically done by users of ISV codes or system administrators who just need to know whom they have to ask for help.

In the former case correctness checking is most likely done interactively on a smaller development cluster, but it might also be included in automated regression testing. The second case must use the hardware and software stack on the system that is to be checked.

While doing correctness checking one has to distinguish *error detection* which is done automatically by tools and *error analysis* which is done by the user to determine the root cause of the error and eventually fix it.

The error detection in ITC is implemented in a special library, *libVTmc*, which always does *online* error detection at runtime of the application. To cover both of the scenarios mentioned above, recording of error reports for later analysis as well as interactive debugging at runtime are both supported. At this time *libVTmc* cannot write a trace file. To switch between correctness checking and performance analysis one has to rerun the application with one of the performance tracing libraries (*libVT* or *libVTfs*).

In some cases special features in Intel® MPI Library are required by *libVTmc*. Therefore this is currently the only MPI for which a *libVTmc* is provided.

The errors are printed to `STDERR` as soon as they are found. Interactive debugging is done with the help of a traditional debugger: if the application is already running under debugger control, then the debugger has the possibility to stop a process when an error is found.

Currently it is necessary to manually set a breakpoint in the function `MessageCheckingBreakpoint()`. This function and debug information about it are contained in the ITC library. Therefore it is possible to set the breakpoint and after a process was stopped, to inspect the parameters of the function which describe what error occurred. In later versions it will also be possible to start a debugger at the time when the error is found.



## 4.2 Usage

### 4.2.1 Inserting ITC

The first step always is to run the application so that libVTmc can intercept all MPI calls. The available methods to achieve this are exactly the same as for normal performance analysis with libVT or libVTfs:

1. Use LD\_PRELOAD (Linux\* only):  
`mpiexec -genv LD_PRELOAD libVTmc.so -n ...`
2. Binary instrumentation(section 3.4.4).
3. Relinking the application (3.1.2).
4. '-check' command line option of mpiexec (Intel® MPI library only).

### 4.2.2 Running with valgrind

For distributed memory checking (LOCAL:MEMORY:INITIALIZATION) and detecting accesses to memory that is owned by MPI and thus should not be touched by the application (LOCAL:MEMORY:ILLEGAL\_ACCESS) it is necessary to run all MPI processes under control of the valgrind memory checker (Linux\* only). Valgrind is an open source memory checker which is available for x86 and Intel® 64 Linux machines free of charge from <http://www.valgrind.org/> and/or packaged by Linux distributors; it is *not* part of the package distributed by Intel and therefore has to be installed separately. Only valgrind versions  $\geq 3.2.0$  are supported.

The recommended way of invoking valgrind is to invoke it directly on the main MPI process and to add the `mpiexec -l` option so that all output printed by valgrind is automatically prefixed with the MPI process rank. ITC detects that `-l` is in effect if the Intel® MPI Library version is 3.0 build 043 or higher and then leaves adding the rank prefix to `mpiexec` also for ITC's own output. One drawback of `-l` is that it leads to a lot of interleaving of lines if processes generate output concurrently; this can be solved by redirecting the output to a file and then either grepping for the output of individual processes (e.g. `grep '^0:'` for rank 0) or sorting the output by rank (`sort -n`).

The LOCAL:MEMORY:ILLEGAL\_ACCESS check causes valgrind reports not just for illegal application accesses (as desired) but also for Intel® MPI Library's own access to the locked memory (not desired, because MPI currently owns it and must read or write it). These reports are normal and the valgrind suppression file in ITC's `lib` directory tells valgrind to not print them, but valgrind must be told about it via its `--suppressions` option.

When the MPI executable is given on the command line, an MPI application could be started under valgrind like this:

```
mpiexec -genv LD_PRELOAD libVTmc.so -l -n <num procs>  
    valgrind --suppressions=$VT_LIB_DIR/impi.supp <application> ...
```

When a wrapper script is used, then it might be possible to trace through the wrapper script by adding the `--trace-children=yes` option, but that could lead to reports about the script interpreter and other programs, so adding valgrind to the actual invocation of the MPI binary is easier.



### 4.2.3 Configuration

Which errors are checked for at runtime is configurable: all errors have a unique name and are categorized in a hierarchy similar to functions. For example, “LOCAL:MEMORY:OVERLAP” is a local check which ensures that memory is not used twice in concurrent MPI operations. The “CHECK” configuration option matches against these full names of each supported error and turns it on or off, like this:

```
# turn all checking off:
# ** matches colons
# * does not
CHECK ** OFF
# selectively turn on specific checks:
# - all local checks
CHECK LOCAL:** ON
# - just one global check
CHECK GLOBAL:MSG:DATATYPE:MISMATCH ON
```

By default ITC checks for all errors and tries to provide as much information about them as possible. In particular it does stack unwinding and reports source code information for each level in the call hierarchy. This can be controlled with the `PCTRACE` configuration option. For performance analysis that option is off by default, but for correctness checking with `libVTmc` it is enabled.

Disabling certain errors serves two purposes: first of all it avoids any report about the disabled errors. Then it can also reduce the overhead for checking if it allows ITC to skip certain code or communication.

Another relevant setting is the `DEADLOCK-TIMEOUT`. This controls the same mechanism to detect deadlocks as in `libVTfs`. For interactive use it is recommended to set it to a small value like “10s” to detect deadlocks quickly without having to wait long for the timeout.

The different levels for the `VERBOSE` configuration of verbosity have the following effects:

- 0 all extra output disabled, only error summary at the end is printed
- 1 adds a summary of configuration options as the application starts (default)
- 2 adds a one-line info message at the beginning by each process with host name, process ID and the normal rank prefix; this can be useful if output is redirected into one file per process because it identifies to which process in the parallel application the output belongs
- 3 adds internal progress messages and a dump of MPI call entry/exit with their parameters and results

### 4.2.4 Analyzing the Results

For interactive debugging the application has to be started so that `stderr` is printed to a console window. Then one can follow which errors are found while the application is running and start analyzing them without having to wait for it to complete. If critical errors are found early on one could even abort the run, fix the problem and restart. This ensures a much faster code and test cycle than a post-mortem analysis.

The output for each error varies, depending on the error: only the relevant information is printed, thus avoiding the need to manually skip over irrelevant information. In general ITC starts with the error name and then continues with a description of the failure.

For each MPI call involved in the error the MPI parameters are dumped. If PC tracing is enabled, ITC also provides a backtrace of source code locations for each call. For entities like requests the



involved calls include the places where a request was created or activated. This helps to track down errors where the problem is not at the place where it is detected.

Because multiple processes might print errors concurrently, each line is prefixed with a tag that includes the rank of the process in `MPI_COMM_WORLD` which reports the problem. MPI applications which use process spawning or attachment are not supported at the moment and therefore that rank is unique.

When the application terminates, ITC does further error checks (e.g. unfreed resources, pending messages). Note that if any process is killed without giving it a chance to clean up (i.e. by sending it a SIGKILL) this final step is not possible. Note that sending a SIGINT to `mpiexec` via kill or pressing `CTRL-C` will cause Intel® MPI Library to abort all processes with such a hard SIGKILL.

## 4.2.5 Debugger Integration

As mentioned earlier, it is currently necessary to manually set a breakpoint in the function `MessageCheckingBreakpoint()`. Immediately after reporting an error on `stderr` this function is called, so the stack backtrace directly leads to the source code location of the MPI call where the error was detected. In addition to the printed error report one can also look at the parameters of the `MessageCheckingBreakpoint()` which contain the same information. It is also possible to look at the actual MPI parameters with the debugger because the initial layer of MPI wrappers in `libVTmc` is always compiled with debug information. This can be useful if the application itself lacks debug information or calls MPI with a complex expression or function call as parameter for which the result is not immediately obvious.

The exact methods to set breakpoints depend on the debugger which is used. Here are some information how it works with specific debuggers. For additional information or other debuggers please refer to the debuggers's user manual.

The first three debuggers mentioned below can be started by Intel® MPI Library by adding the `-tv`, `-gdb` or `-idb` options to the command line of `mpiexec` or `mpirun`. Allinea's DDT can be reconfigured to attach to MPI jobs that it starts.

Using debuggers like that and `valgrind` are mutually exclusive because the debuggers would try to debug `valgrind`, not the actual application. The `valgrind --db-attach` option does not work out-of-the-box either because each process would try to read from the terminal. One solution that is known to work on some systems for analyzing at least `valgrind`'s reports is to start each process in its own X terminal:

```
mpiexec -genv LD_PRELOAD libVTmc.so -l -n <numprocs> xterm -e bash -c
    'valgrind --db-attach=yes --suppressions=$VT_LIB_DIR/impi.sup
    <app>; echo press return; read'
```

In that case ITC's error handling still occurs outside the debugger, so those errors have to be analyzed based on the printed reports.

### 4.2.5.1 Etnus TotalView\* debugger

For TotalView\* it is necessary to pay attention that the breakpoint should be set for all processes. For TotalView\* there are several ways to automate procedure of setting breakpoints. Mostly it depends how common it is planned to use this automation.

If it is planned to apply it only for the current program, one can create the file `filename.tvd` (filename being the name of the executable) in the working directory in advance and put the following line into it:





## 4.2. USAGE

---

```
dfocus gW2 dbreak MessageCheckingBreakpoint
```

Alternatively one can set the breakpoint in the TotalView\* GUI and save breakpoints, which will also create this file and then reuse the settings for further debug sessions with the same executable.

To apply setting this breakpoint for all programs in current working directory one can create a file `.tvdrc` with the following lines (or add them if it already exists):

```
proc my_callback {_id} {
    if { $_id == 2 } {
        dfocus p$_id dbreak MessageCheckingBreakpoint
    }

    if { $_id > 2 } {
        dfocus p$_id denable -a
    }
}
dset TV::process_load_callbacks ::my_callback
```

To apply this for all debugging sessions, it is necessary to add these lines to the file `$HOME/.totalview/tvdrc`. Note there is no dot in the name of this file.

### 4.2.5.2 GDB, the GNU\* Symbolic Debugger

To automate the procedure of setting breakpoints, gdb supports executing commands automatically. To apply setting this breakpoint for all programs in the current working directory one can create a file `.gdbinit` with the following lines (or add them if it already exists):

```
set breakpoint pending on
break MessageCheckingBreakpoint
```

Due to the order in which files are processed, placing the same commands in a `.gdbinit` file in the home directory does not work because the main binary is not loaded yet. As a workaround one can put the following commands into `~/gdbinit` and then start MPI applications with the normal run command:

```
define hook-run
    # important, output is expected by MPI startup helper
    echo Starting program...
    # allow pending breakpoint
    set breakpoint pending on
    # set breakpoint now or as soon as function becomes available
    break MessageCheckingBreakpoint
    # restore default behavior
    set breakpoint pending auto
end
```

### 4.2.5.3 IDB, the Intel® Debugger

For idb the following way is used to automate procedure of setting breakpoints. To apply setting this breakpoint for all programs in the current working directory one can create a file `.dbxinit` with the following line (or add them if it already exists):

```
stop MessageCheckingBreakpoint
```

Alternatively one can add this command to a `.dbxinit` file in the home directory, then it is applied to all programs. A warning about not being able to set this breakpoint in programs without `libVTmc` included is normal and can be ignored.



#### 4.2.5.4 Allinea's Distributed Debugging Tool, DDT

DDT must be configured to run the user's application with the necessary Intel® libraries pre-loaded. This is best achieved from the "Run" dialog by selecting the Session/Options menu and choosing "Intel MPI Library" along with selecting the "Submit through queue or configure own mpirun command option". In the "Submit Command" box enter (without line breaks):

```
mpirun -genv LD_PRELOAD libVTmc.so -genv VT_DEADLOCK_TIMEOUT 20s
      -genv VT_DEADLOCK_WARNING 25s -n NUM_PROCS_TAG
      DDTPATH_TAG/bin/ddt-debugger
```

Other boxes can remain empty, and then click "Ok".

Start the application by pressing the submit button on DDT's job launch dialog. When the application is ready, select the "Control/Add Breakpoint" menu and add a breakpoint at the function MessageCheckingBreakpoint.

Continue to run and debug your application as normal, the program will stop automatically at MessageCheckingBreakpoint when an MPI error is detected. You may use the parallel stack browser to find the processes that are stopped and select any of these processes. The local variables in this function will identify the error type, the number of errors so far, and the error message.

You may also set a condition on this breakpoint from the Breakpoints tab, or "Add Breakpoint" menu, for example to stop only after 20 errors are reported use a condition of "reportnumber > 20".

## 4.3 Error Detection

### 4.3.1 Supported Errors

Errors fall into two different categories:

**local** checks only need information available in the process itself and thus do not require additional communication between processes

**global** information from other processes is required

Another aspect of errors is whether the application can continue after they occurred. Minor problems which may or may not require fixing are reported as warnings and allow the application to continue, but they lead to resource leaks or portability problems. Real errors are invalid operations that can only be skipped to proceed, but this either changes the application semantic (e.g. transmission errors) or leads to follow-up errors (e.g. skipping an invalid send can lead to a deadlock because of the missing message). Fatal errors cannot be resolved at all and require an application shutdown.

Problems are counted separately per process. Disabled errors are neither reported nor counted, even if they still happen to be detected. The application will be aborted as soon as a certain number of errors are encountered: obviously the first fatal error always requires an abort. Once the number of errors reaches **CHECK-MAX-ERRORS** or the total number of reports (regardless whether they are warnings or errors) reaches **CHECK-MAX-REPORTS** (whatever comes first), the application is aborted. These limits apply to each process separately. Even if one process gets stopped, the other processes are allowed to continue to see whether they run into further errors. The whole application is then aborted after a certain grace period. This timeout can be set via **CHECK-TIMEOUT**.



### 4.3. ERROR DETECTION

The default for `CHECK-MAX-ERRORS` is 1 so that the first error already aborts, whereas `CHECK-MAX-REPORTS` is at 100 and thus that many warnings errors are allowed. Setting both values to 0 removes the limits. Setting `CHECK-MAX-REPORTS` to 1 turns the first warning into a reason to abort.

When using an interactive debugger the limits can be set to 0 manually and thus removed, because the user can decide to abort using the normal debugger facilities for application shutdown. If he chooses to continue then ITC will skip over warnings and non-fatal errors and try to proceed. Fatal errors still force ITC to abort the application.

The type of all supported errors is listed in tables 4.1 and 4.2. The description provides just a few keywords for each error, a more detailed description can be found in the following sections.

Error Name	Type	Description
LOCAL:EXIT:SIGNAL	fatal	process terminated by fatal signal
LOCAL:EXIT:BEFORE_MPI_FINALIZE	fatal	process exits without calling MPI_Finalize()
LOCAL:MPI:CALL_FAILED	depends on MPI and error	MPI itself or wrapper detects an error
LOCAL:MEMORY:OVERLAP	warning	multiple MPI operations are started using the same memory
LOCAL:MEMORY:ILLEGAL_MODIFICATION	error	data modified while owned by MPI
LOCAL:MEMORY:INACCESSIBLE	error	buffer given to MPI cannot be read or written
LOCAL:MEMORY:ILLEGAL_ACCESS	error	read or write access to memory currently owned by MPI
LOCAL:MEMORY:INITIALIZATION	error	distributed memory checking
LOCAL:REQUEST:ILLEGAL_CALL	error	invalid sequence of calls
LOCAL:REQUEST:NOT_FREED	warning	program creates suspiciously high number of requests or exits with pending requests
LOCAL:REQUEST:PREMATURE_FREE	warning	freeing an active receive request is discouraged
LOCAL:DATATYPE:NOT_FREED	warning	program creates high number of datatypes
LOCAL:BUFFER:INSUFFICIENT_BUFFER	warning	not enough space for buffered send

Table 4.1: Supported Local Errors

#### 4.3.2 How it works

Understanding how ITC finds the various supported errors is important because it helps to understand what the different configuration options mean, what ITC can do and what it cannot, and how to interpret the results.

Just as for performance analysis, ITC intercepts all MPI calls using the MPI profiling interface. It has different wrappers for each MPI call. In these wrappers it can execute additional checks not



Error Name	Type	Description
GLOBAL:MSG/COLLECTIVE:DATATYPE:MISMATCH	error	the type signature does not match
GLOBAL:MSG/COLLECTIVE:DATA_TRANSMISSION_CORRUPTED	error	data modified during transmission
GLOBAL:MSG:PENDING	warning	program terminates with unreceived messages
GLOBAL:DEADLOCK:HARD	fatal	a cycle of processes waiting for each other
GLOBAL:DEADLOCK:POTENTIAL	fatal <sup>a</sup>	a cycle of processes, one or more in blocking send
GLOBAL:DEADLOCK:NO_PROGRESS	warning	warning when application might be stuck
GLOBAL:COLLECTIVE:OPERATION_MISMATCH	error	processes enter different collective operations
GLOBAL:COLLECTIVE:SIZE_MISMATCH	error	more or less data than expected
GLOBAL:COLLECTIVE:REDUCTION_OPERATION_MISMATCH	error	reduction operation inconsistent
GLOBAL:COLLECTIVE:ROOT_MISMATCH	error	root parameter inconsistent
GLOBAL:COLLECTIVE:INVALID_PARAMETER	error	invalid parameter for collective operation
GLOBAL:COLLECTIVE:COMM_FREE_MISMATCH	warning	MPI_Comm_free() must be called collectively

<sup>a</sup>if check is enabled, otherwise it depends on the MPI implementation

Table 4.2: Supported Global Errors



### 4.3. ERROR DETECTION

---

normally done by the MPI implementation itself.

For global checks ITC uses two different methods for transmitting the additional information: in collective operations it executes another collective operation before or after the original operation, using the same communicator<sup>1</sup>. For point-to-point communication it sends one additional message over a shadow communicator for each message sent by the application.

In addition to exchanging this extra data via MPI itself, ITC also creates one background thread per process. These threads are connected to each other via TCP sockets and thus can communicate with each other even while MPI is being used by the main application thread.

For distributed memory checking and locking memory that the application should not access, ITC interacts with valgrind (section 4.2.2) via valgrind's client request mechanism. Valgrind tracks definedness of memory (i.e. whether it was initialized or not) within a process; ITC extends that mechanism to the whole application by transmitting this additional information between processes using the same methods which also transmit the additional data type information and restoring the correct valgrind state at the recipient.

Without valgrind the `LOCAL:MEMORY:ILLEGAL_MODIFICATION` check is limited to reporting write accesses which modified buffers; typically this is detected long after the fact. With valgrind, memory which the application hands over to MPI is set to "inaccessible" in valgrind by ITC and accessibility is restored when ownership is transferred back. In between any access by the application is flagged by valgrind right at the point where it occurs. Suppressions are used to avoid reports for the required accesses to the locked memory by the MPI library itself.

#### 4.3.2.1 Parameter Checking (`LOCAL:MPI:CALL_FAILED`)

Most parameters are checked by the MPI implementation itself. ITC ensures that the MPI does not abort when it finds an error, but rather reports back the error via a function's result code. Then ITC looks at the error class and depending on the function where the error occurred decides whether the error has to be considered as a warning or a real error. As a general rule, calls which free resources lead to warnings and everything else is an error. The error report of such a problem includes a stack backtrace (if enabled) and the error message generated by MPI.

Note that in order to catch MPI errors this way ITC overrides any error handlers installed by the application. Errors will always be reported, even if the application or test program sets an error handler to skip over known and/or intentionally bad calls. Because the MPI standard does not guarantee that errors are detected and that proceeding after a detected error is possible, such programs are not portable and should be fixed. ITC on the other hand knows that proceeding despite an error is allowed by all supported MPIs and thus none of the parameter errors is considered a hard error.

Communicator handles are checked right at the start of an MPI wrapper by calling an MPI function which is expected to check its arguments for correctness. Datatype handles are tracked and then checked by ITC itself. The extra parameter check is visible when investigating such an error in a debugger and although perhaps unexpected is perfectly normal. It is done to centralize the error checking.

#### 4.3.2.2 Premature Exit (`LOCAL:EXIT`)

ITC monitors the ways how a process can abort prematurely: otherwise fatal signals are caught in ITC signal handlers. An `atexit()` handler detects situations where the application or some library

---

<sup>1</sup>This is similar to the method described in "Collective Error Detection for MPI Collective Operations", Chris Falzone, Anthony Chan, Ewing Lusk, William Gropp, <http://www.mcs.anl.gov/~gropp/bib/papers/2005/collective-checking.pdf>



decides to quit. `MPI_Abort()` is also intercepted.

This error is presented just like a `LOCAL:MPI:CALL_FAILED`, with the same options for investigating the problem in a debugger. However, these are hard errors and the application cannot continue to run.

#### 4.3.2.3 Overlapping Memory (`LOCAL:MEMORY:OVERLAP`)

ITC keeps track of memory currently in use by MPI and before starting a new operation, checks that the memory that it references is not in use already.

The MPI standard explicitly transfers ownership of memory to MPI even for send operations. The application is not allowed to read it while a send operation is active and must not setup another send operation which reads it either. The rationale is that the MPI might modify the data in place before sending it and revert the change afterwards. In practice MPI implementation do not modify the memory, so this is a minor problem and just triggers a warning.

Obviously, writing into the same memory twice in possibly random order or writing into memory which the MPI might read from is a real error. However, detecting these real errors is harder for message receives because the size of the buffer given to MPI might be larger than the actual message: even if buffers overlap, the messages might be small enough to not lead to writes into the same memory. Because the overlap check is done when a send buffer is handed over to MPI, only a warning is generated. The application might be able to continue normally, but the source code should be fixed because under a strict interpretation of the MPI standard using the same buffer twice is already illegal even if the actual messages do not overlap.

Because the problem might be at the place where the memory was given to MPI initially and not where it is reused, ITC also provides both call stacks.

#### 4.3.2.4 Detecting illegal buffer modifications (`LOCAL:MEMORY:ILLEGAL_MODIFICATION`)

MPI owns the memory that active communication references. The application must not touch it during that time. Illegal writes into buffers that the MPI is asked to send are detected by calculating a checksum of the data immediately before the request is activated and comparing it against a checksum when the send completes. If the checksum is different, someone must have modified the buffer. The reported `LOCAL:MEMORY:ILLEGAL_MODIFICATION` is a real error.

This problem is more common with non-blocking communication because the application gets control back while MPI still owns the buffer and then might accidentally modify the buffer. For non-blocking communication the callstacks of where the send was initiated and where it completed are provided. For persistent requests it is also shown where it was created.

The problem might also occur for blocking communication, for example when the MPI implementation incorrectly modifies the send buffer, the program is multithreaded and writes into it or other communication happens to write into the buffer. In this case only the callstack of the blocking call where the problem was detected gets printed.

Strictly speaking, reads are also illegal because the MPI standard makes no guaranteed about the content of buffers while MPI owns them. Because reads do not modify buffers, such errors are not detected. Writes are also not detected when they happen (which would make debugging a lot easier) but only later when the damage is detected.



## 4.3. ERROR DETECTION

---

### 4.3.2.5 Buffer given to MPI cannot be read or written (LOCAL:MEMORY:INACCESSIBLE)

During the check for `LOCAL:MEMORY:ILLEGAL_MODIFICATION` of a send buffer ITC will read each byte in the buffer once. This works for contiguous as well as non-contiguous datatypes. If any byte cannot be read because the memory is inaccessible, a `LOCAL:MEMORY:INACCESSIBLE` is reported. This is an error because it is only possible to proceed by skipping the entire operation.

Disabling the `LOCAL:MEMORY:ILLEGAL_MODIFICATION` check also disables the accessibility check and send operations are then treated like receive operations: for receive operations no similar check is performed because the MPI standard does not say explicitly that the whole receive buffer has to be accessible—only the part into which an incoming message actually gets copied must be writable. Violations of that rule are caught and reported as fatal `LOCAL:EXIT:SIGNAL` errors.

### 4.3.2.6 Distributed Memory Checking (LOCAL:MEMORY:INITIALIZATION)

This feature is enabled by default if all processes run under `valgrind` (see section 4.2.2). If that is not the case, it is disabled. If in doubt, check the configuration summary at the beginning of the run to see whether this feature was enabled or not. There are no ITC error reports with this type; `valgrind`'s error reports have to be watched instead to find problems related to memory initialization. See the section “Use of uninitialised values” in `valgrind`'s user guide for details.

If enabled, then `valgrind`'s tracking of memory definedness is extended to the whole application. For applications which transmit partially initialized data between processes, this avoids two cases:

**false positive** sending the message with the partially initialized data triggers a `valgrind` report for send or write system calls at the sender side

**false negative** at the recipient, `valgrind` incorrectly assumes that all incoming data is completely initialized and thus will not warn if the uninitialized data influences the control flow in the recipient; normally it would report that

To handle the false positive case `valgrind` must have been started with the suppression file provided with ITC. The `local/memory/valgrind` example demonstrates both cases.

Turning this feature off is useful if the application is supposed to be written in such a way that it never transmits uninitialized data. In that case ITC's suppression file should not be used because it would suppress warnings at the sender and the `LOCAL:MEMORY:ILLEGAL_ACCESS` must be disabled as it would cause extra `valgrind` reports.

### 4.3.2.7 Illegal Memory Access (LOCAL:MEMORY:ILLEGAL\_ACCESS)

This feature depends on `valgrind` the same way as `LOCAL:MEMORY:INITIALIZATION`. This check goes beyond `LOCAL:MEMORY:ILLEGAL_MODIFICATION` by detecting also reads and reporting them through `valgrind` at the point where the access happens. Disabling it might improve performance and help if the provided suppression rules do not manage to suppress reports about valid accesses to locked memory.

### 4.3.2.8 Request Handling (LOCAL:REQUEST)

When the program terminates ITC prints a list of all unfreed MPI requests together with their status. Unfreed requests are usually currently active and application should have checked their



status before terminating. Persistent requests can also be passive and need to be freed explicitly with `MPI_Request_free()`.

Not freeing requests blocks resources inside the MPI and can cause application failures. Each time the total number of active requests or inactive persistent requests exceeds another multiple of the `CHECK-MAX-REQUESTS` threshold (i.e. after 100, 200, 300, ... requests) a `LOCAL:REQUEST:NOT_FREED` warning is printed with a summary of the most frequent calls where those requests were created. The number of calls is configured via `CHECK-LEAK-REPORT-SIZE`.

Finalizing the application with pending requests is not an error according to the MPI standard, but is not good practice and can potentially mask real problems. Therefore a request leak report will be always generated during finalize if at least one request was not freed.

If there are pending receives the check for pending incoming messages is disabled because some or all of them might match with the pending receives.

Note that active requests that were explicitly delete with `MPI_Request_free()` will show up in another leak report if they have not completed by the time when the application terminates. Most likely this is due to not having a matching send or receive elsewhere in the application, but it might also be caused by posting and deleting a request and then terminating without giving it sufficient time to complete.

The MPI standard recommends that receive requests are not freed before they have completed. Otherwise it is impossible to determine whether the receive buffer can be read. Although not strictly marked an error in the standard, a `LOCAL:REQUEST:PREMATURE_FREE` warning is reported if the application frees such a request prematurely. For send requests the standard describes a method how the application can determine that it is safe to reuse the buffer, thus this is not reported as an error.

In both cases actually deleting the request is deferred in a way which is transparent to the application: at the exit from all MPI calls which communicate with other processes ITC will check whether any of them has completed and then execute the normal checking that it does at completion of a request (`LOCAL:MEMORY:ILLEGAL_MODIFICATION`) and also keep track of the ownership of the memory (`LOCAL:MEMORY:OVERLAP`).

In addition not freeing a request or freeing it too early, persistent requests also require that calls follow a certain sequence: create the request, start it and check for completion (can be repeated multiple times), delete the request. Starting a request while it is still active is an error which is reported as `LOCAL:REQUEST:ILLEGAL_CALL`. Checking for completion of an inactive persistent request on the other hand is not an error.

#### 4.3.2.9 Datatype Handling (`LOCAL:DATATYPE`)

Unfreed datatypes can cause the same problems as unfreed requests, so the same kind of leak report is generated for them when their number exceeds `CHECK-MAX-DATATYPES`. However, because not freeing datatypes is common practice there is no leak report during finalize unless their number exceeds the threshold at that time. That is in contrast to requests which are always reported then.

#### 4.3.2.10 Buffered Sends (`LOCAL:BUFFER:INSUFFICIENT_BUFFER`)

ITC intercepts all calls related to buffered sends and simulates the worst-case scenario that the application has to be prepared for according to the standard. By default (`GLOBAL:DEADLOCK:POTENTIAL` enabled) it also ensures that the sends do not complete before





### 4.3. ERROR DETECTION

---

there is a matching receive.

By doing both it detects several different error scenarios which all can lead to insufficient available buffer errors that might not occur depending on timing and/or MPI implementation aspects:

**Buffer Size** The most obvious error is that the application did not reserve enough buffer to store the message(s), perhaps because it did not actually calculate the size with `MPI_Pack_size()` or forgot to add the `MPI_BSEND_OVERHEAD`. This might not show up if the MPI implementation bypasses the buffer, e.g. for large messages. Example: `local/buffered_send/size`.

**Race Condition** Memory becomes available again only when the oldest messages are transmitted. It is the responsibility of the application to ensure that this happens in time before the buffer is required again; without suitable synchronization an application might run only because it is lucky and the recipients enter their receives early enough. Examples: `local/buffered_send/race`, `local/buffered_send/policy`.

**Deadlock** `MPI_Buffer_detach()` will block until all messages inside the buffer have been sent. This can lead to the same (potential) deadlocks as normal sends. Example: `local/buffered_send/deadlock`.

Because it is critical to understand how the buffer is currently being used when a new buffered send does not find enough free space to proceed, the `LOCAL:BUFFER:INSUFFICIENT_BUFFER` error message contains all information about free space, active and completed messages and the corresponding memory ranges. Memory ranges are given using the `[start address, end address[` notation where the end address is not part of the memory range. For convenience the number of bytes in each range is also printed. For messages this includes the `MPI_BSEND_OVERHEAD`, so even empty messages have a non-zero size.

#### 4.3.2.11 Deadlocks (GLOBAL:DEADLOCK)

Deadlocks are detected via a heuristic: the background thread in each process cooperates with the MPI wrappers to detect that the process is stuck in a certain MPI call. That alone is not an error because some other processes might still make progress. Therefore the background threads communicate if at least one process appears to be stuck. If *all* processes are stuck, this is treated as a deadlock. The timeout after which a process and thus the application is considered as stuck is configurable with [DEADLOCK-TIMEOUT](#).

The timeout defaults to 1 minute which should be long enough to ensure that even very long running MPI operations are not incorrectly detected as being stuck. In applications which are known to execute correct MPI calls much faster, it is advisable to decrease this timeout to detect a deadlock sooner.

This heuristic fails if the application is using non-blocking calls like `MPI_Test()` to poll for completion of an operation which can no longer complete. This case is covered by another heuristic: if the average time spent inside the last MPI call of each process exceeds the [DEADLOCK-WARNING](#) threshold, then a `GLOBAL:DEADLOCK:NO_PROGRESS\` warning is printed, but the application is allowed to continue because the same high average blocking time also occurs in correct application with a high load imbalance. For the same reason the warning threshold is also higher than the hard deadlock timeout.

To help analyzing the deadlock, ITC prints the callstack of all process. A real hard deadlock exists if there is a cycle of processes waiting for data from the previous process in the cycle. This data dependency can be an explicit `MPI_Recv()`, but also a collective operation like `MPI_Reduce()`.

If message are involved in the cycle, then it might help to replace send or receive calls with their non-blocking variant. If a collective operation prevents one process from reaching a message

send that another process is waiting for, then reordering the message send and the collective operation in the first process would fix the problem.

Another reason could be messages which were accidentally sent to the wrong process. This can be checked in debuggers which support that by looking at the pending message queues. In the future ITC might also support visualizing the program run in ITA in case of an error. This would help to find messages which were not only sent to the wrong process, but also received by that processes and thus do not show up in the pending message queue.

In addition to the real hard deadlock from which the application cannot recover MPI applications might also contain potential deadlocks: the MPI standard does not guarantee that a blocking send returns unless the recipient calls a matching receive. In the simplest case of a head-to-head send with two processes, both enter a send and then the receive for the message that the peer just sent. This deadlocks unless the MPI buffers the message completely and returns from the send without waiting for the corresponding receive.

Because this relies on undocumented behaviour of MPI implementations this is a hard to detect portability problem. ITC detects these `GLOBAL:DEADLOCK:POTENTIAL` errors by turning each normal send into a synchronous send. The MPI standard then guarantees that the send blocks until the corresponding receive is at least started. Send requests are also converted to their synchronous counterparts; they block in the call which waits for completion. With these changes any potential deadlock automatically leads to a real deadlock at runtime and will be handled as described above. To distinguish between the two types, check whether any process is stuck in a send function. Due to this way of detecting it, even the normally non-critical potential deadlocks do not allow the application to proceed.

#### 4.3.2.12 Checking message transmission (`GLOBAL:MSG`)

For each application message, another extra message is sent which includes:

- a datatype signature hash code (for `GLOBAL:MSG:DATATYPE:MISMATCH`)
- a checksum of the data (for `GLOBAL:MSG:DATA_TRANSMISSION_CORRUPTED`)
- a stack backtrace for the place where the message was sent (for both of these errors and also for `GLOBAL:MSG:PENDING`)

Only disabling of all of these three errors avoids the overhead for the extra messages.

Buffered messages which are not received lead to a resource leak. They are detected each time a communicator is freed or (if a communicator does not get freed) when the application terminates.

The information provided includes a callstack of where the message was sent as well as the current callstack where the error is detected.

#### 4.3.2.13 Datatype mismatches (`GLOBAL:*.DATATYPE:MISMATCH`)

Datatype mismatches are detected by calculating a hash value of the datatype signature and comparing that hash value: if the hash values are different, the type signatures must have been different too and an error is reported. Because the information about the full type signature at the sender is not available, it has to be deduced from the function call parameters and/or source code locations where the data is transmitted.

If the hash values are identical, then there is some small chance that the signatures were different



### 4.3. ERROR DETECTION

---

although no error is reported. Because of the choice of a very advanced hash function<sup>2</sup> this is very unlikely. This hash function can also be calculated more efficiently than traditional hash functions.

#### 4.3.2.14 Data modified during transmission (GLOBAL:\*:DATA\_TRANSMISSION\_CORRUPTED)

After checking that the datatype signatures in a point-to-point message transfer or collective data gather/scatter operation at sender and receiver match, ITC also verifies that the data was transferred correctly by comparing additional checksums that are calculated inside the sending and receiving process. This adds another end-to-end data integrity check which will fail if any of the components involved in the data transmission malfunctioned (MPI layer, device drivers, hardware).

In cases where this GLOBAL:\*:DATA\_TRANSMISSION\_CORRUPTED error is obviously the result of some other error, it is not reported separately. This currently works for truncated message receives and datatype mismatches.

#### 4.3.2.15 Checking of Collective Operations (GLOBAL:COLLECTIVE)

Checking correct usage of collective operations is easier than checking messages. At the beginning of each operation, ITC broadcasts the same data from rank #0 of the communicator. This data includes:

- type of the operation
- root (zero if not applicable)
- reduction type (predefined types only)

Now all involved processes check these parameters against their own parameters and report an error in case of a mismatch. If the type is the same, for collective operations with a root process that rank and for reduce operations the reduction operation are also checked. The GLOBAL:COLLECTIVE:REDUCTION\_OPERATION\_MISMATCH error can only be detected for predefined reduction operation because it is impossible to verify whether the program code associated with a custom reduction operation has the same semantic on all processes. After this step depending on the operation different other parameters are also shared between the processes and checked.

Invalid parameters like MPI\_DATATYPE\_NULL where a valid datatype is required are detected while checking the parameters. They are reported as one GLOBAL:COLLECTIVE:INVALID\_PARAMETER error with a description of the parameter which is invalid in each process. This leads to less output than printing one error for each process.

If any of these checks fails, the original operation is not executed on any process. Therefore proceeding is possible, but application semantic will be affected.

#### 4.3.2.16 Freeing communicators (GLOBAL:COLLECTIVE:COMM\_FREE\_MISMATCH)

A mistake related to MPI\_Comm\_free() is freeing them in different orders on the involved processes. The MPI standard specifies that MPI\_Comm\_free() must be entered by the processes in the communicator collectively. Some MPIs including Intel® MPI Library deadlock if this rule is broken, whereas others implement MPI\_Comm\_free() as a local call with no communication.

---

<sup>2</sup>"Hash functions for MPI datatypes", Julien Langou, George Bosilca, Graham Fagg, Jack Dongarra, <http://www.cs.utk.edu/~library/TechReports/2005/ut-cs-05-552.pdf>



To ensure that this error is detected all the time, ITC treats `MPI_Comm_free()` just like the other collective operations. There is no special error message for `GLOBAL:COLLECTIVE:COMM_FREE_MISMATCH`, it will be reported as a mismatch between collective calls (`GLOBAL:COLLECTIVE:OPERATION_MISMATCH`) or a deadlock, so `GLOBAL:COLLECTIVE:COMM_FREE_MISMATCH` just refers to the check which enables or disables this test, not a specific error instance.

---

## Chapter 5

# Time Stamping

ITC assigns a local time stamp to each event that it records. A time stamp consists of two parts which together guarantee that each time stamp is unique:

**Clock Tick** counts how often the timing source incremented since the start of the run.

**Event Counter** is incremented for each time stamp which happens to have the same clock tick as the previous time stamp. In the unlikely situation that the event counter overflows, ITC artificially increments the clock tick. When running ITC with `VERBOSE > 2`, it will print the maximum number of events on the same clock tick during the whole application run. A non-zero number implies that the clock resolution was too low to distinguish different events.

Both counters are stored in a 64 bit unsigned integer with the event counter in the low-order bits. Legacy applications can still convert time stamps as found in a trace file to seconds by multiplying the time stamp with the nominal clock period defined in the trace file header: if the event counter is zero, this will not incur any error at all. Otherwise the error is most likely still very small. The accurate solution however is to shift the time stamp by the amount specified as “event bits” in the trace header (and thus removing the event counter), then multiplying with the nominal clock period and 2 to the power of “event bits”.

Currently ITC uses 51 bits for clock ticks, which is large enough to count  $2^{51}$ ns, which equals  $2^{51}/1e9/60/60/24 \geq 26$  days before the counter overflows. At the same time with a clock of only ms resolution, you can distinguish  $2^{64-51} = 8192$  different events with the same clock tick, which are events with a duration of 0.1us.

Before writing the events into the global trace file, local time stamps are replaced with global ones by modifying their clock tick. A situation where time stamps with different local clock ticks fall on the same global clock tick is avoided by ensuring that global clock ticks are always larger than local ones.

The nominal clock period in the trace file is chosen so that it is sufficiently small to capture the offsets between nodes as well as the clock correction: both leads to fractions of the real clock period and rounding errors would be incurred when storing the trace with the real clock period. The real clock period might be hard to figure out exactly anyway. Also, the clock ticks are scaled so that the whole run takes exactly as long as determined with `gettimeofday()` on the master process.

## 5.1 Clock Synchronization

By default ITC synchronizes the different clocks at the start and at the end of a program run by exchanging messages in a fashion similar to the Network Time Protocol (NTP): one process is treated as the master and its clock becomes the global clock of the whole application run. During clock synchronization, the master process receives a message from a child process and replies by sending its current time stamp. The child process then stores that time stamp together with its own local send and receive time stamps. One message is exchanged with each child, then the cycles starts again with the first child until `SYNC-MAX-MESSAGES` have been exchanged between master and each child or the total duration of the synchronization exceeds `SYNC-MAX-DURATION`.

ITC can handle timers which are already synchronized among all process on a node (`SYNCED-HOST`) and then only does the message exchange between nodes. If the clock is even synchronized across the whole cluster (`SYNCED-CLUSTER`), then no synchronization is done by ITC at all.

The gathered data of one message exchange session is used by the child processes to calculate the offset between its clock and the master clock: it is assumed that the duration of messages with equal size is equally fast in both directions, so that the average of local send and receive time coincides with the master time stamp in the middle of the message exchange. To reduce the noise, the 10% message pairs with the highest local round-trip time are ignored because those are the ones which most likely suffered from not running either process in time to react in a timely fashion or other external delays.

With clock synchronization at the start and end ITC's clock correction uses a linear transformation, that is a scaling local clock ticks and shifting them, which is calculated by linear regression of all available sample data. If the application also calls `VT_timesync()` during the run, then clock correction is done with a piece-wise interpolation: the data of each message exchange session is condensed into one pair of local and master time by averaging all data points, then a constrained spline is constructed which goes through all of the condensed points and has a contiguous first derivative at each of these joints.

***int VT\_timesync (void)***

Gathers data needed for clock synchronization.

This is a collective call, so all processes which were started together must call this function or it will block.

This function does not work if processes were spawned dynamically.

**Fortran**

VTTIMESYNC( ierr )

## 5.2 Choosing a Timer

A good timer has the following properties:

- high resolution (one order of magnitude higher than the resolution of the events that are to be traced)
- low overhead



## 5.2. CHOOSING A TIMER

---

- linearly increasing values for a long period of time (at least for the duration of a program run); in particular it should not jump forwards or backwards

ITC supports several different timers. Because the quality of these timers depends on factors which are hard to predict (like specific OS bugs, available hardware and so on), a test program is provided which can be run to answer the following questions:

- What is the resolution of a timer?
- What is its overhead?
- How well does clock synchronization work with the default linear transformation?
- If it does not work well, how often does the application have to synchronize to achieve good non-linear interpolation?

To test the quality of each timer, link the `timerperformance.c` program from the examples directory. The makefile already has a target “`vttimertest`” (linked against `libVT` and `MPI`) and for “`timertestcs`” (linked against `libVTcs` and no `MPI`). Use the `MPI` version if you have `MPI`, because `libVT` supports all the normal timers from `libVTcs` plus “`MPI_Wtime`” and because only the `MPI` version can test whether the clock increases linearly by time-stamping message exchanges.

To get a list of supported timers, run with the configuration option `TIMER` set to `LIST`. This can be done easily by setting the `VT_TIMER` environment variable. The subsections below have more information about possible choices, but not all of them may be available on each system.

To test an individual timer, run the binary with `TIMER` set to the name of the timer to be tested. It will repeatedly acquire time stamps and then for each process (“`vttimertest`”) or the current machine (“`timertestcs`”) print a histogram of the clock increments observed. A good timer has most increments close or equal to the minimum clock increment that it can measure. Bad clocks have a very high minimum clock increment (a bad resolution) or only occasionally increment by a smaller amount.

Here is a the output of “`timertestcs`” one a machine with a good `gettimeofday()` clock:

```
bash$ VT_TIMER=gettimeofday ./timertestcs
performance: 2323603 calls in 5.000s wall clock time = 2.152us/call =
              464720 calls/s
measured clock period/frequency vs. nominal:
  1.000us/1.000MHz vs. 1.000us/1.000MHz
overhead for sampling loop: 758957 clock ticks (= 758.958ms)
  for 10000000 iterations = 0 ticks/iteration
average increase: 2 clock ticks = 2.244us = 0.446MHz
median increase: 2 clock ticks = 2.000us = 0.500MHz
<    0 ticks = 0.00s : 0
<    1 ticks = 1.00us: 0
>=   1 ticks = 1.00us: ##### 2261760
>=  501 ticks = 501.00us: 1
>= 1001 ticks = 1.00ms: 0
...
```

The additional information at the top starts with the performance (and thus overhead) of the timer. The next line compares the measured clock period (calculated as elapsed wall clock time divided by clock ticks in the measurement interval) against the one that the timer is said to have; for `gettimeofday()` this is not useful, but for example `CPU` cycle counters (details below) there might be differences. Similarly, the overhead for an empty loop with a dummy function call is only relevant for a timer like `CPU` cycle counters with a very high precision. For that counter however the



overhead caused by the loop is considerable, so during the measurement of the clock increments ITC subtracts the loop overhead.

Here is an example with the CPU cycle counter as timer:

```
bash$ VT_TIMER=CPU ./timertestcs
performance: 3432873 calls in 5.000s wall clock time = 1.457us/call =
           686535 calls/s
measured clock period/frequency vs. nominal:
   0.418ns/2392.218MHz vs. 0.418ns/2392.356MHz
overhead for sampling loop: 1913800372 clock ticks (= 800.011ms)
   for 10000000 iterations = 191 ticks/iteration
average increase: 3476 clock ticks = 1.453us = 0.688MHz
median increase: 3473 clock ticks = 1.452us = 0.689MHz
<    0 ticks = 0.00s : 0
<    1 ticks = 0.42ns: 0
>=   1 ticks = 0.42ns: 0
>=  501 ticks = 209.43ns: 0
>= 1001 ticks = 418.44ns: 0
>= 1501 ticks = 627.45ns: 0
>= 2001 ticks = 836.46ns: 0
>= 2501 ticks = 1.05us: 0
>= 3001 ticks = 1.25us: ##### 3282286
>= 3501 ticks = 1.46us: 587
>= 4001 ticks = 1.67us: 8
>= 4501 ticks = 1.88us: 1
>= 5001 ticks = 2.09us: 869
```

Testing whether the timer increases linearly is more difficult. It is done by comparing the send and receive time stamps of ping-pong message exchanges between two processes after ITC has applied its time synchronization algorithm to them: the algorithm will scale and shift the time stamps based on the assumption that data transfer in both directions is equally fast. So if the synchronization works, the average difference between the duration of messages in one direction minus the duration of the replies has to be zero. The visualization of the trace “timertest.stf” should show equilateral triangles.

If the timer increases linearly, then one set of correction parameters applies to the whole trace. If it does not, then clock synchronization might be good in one part of the trace and bad in another or even more obvious, be biased towards one process in one part with a positive difference and biased towards the other in another part with a negative difference. In either case tweaking the correction parameters would fix the time stamps of one data exchange, but just worsen the time stamps of another.

When running the MPI “vttimertest” with two or more processes it will do a short burst of data exchanges between each pair of processes, then sleep for 10 seconds. This cycle is repeated for a total runtime of 30 seconds. This total duration can be modified by giving the number of seconds as command line parameter. Another argument on the command line also overrides the duration of the sleep. After MPI\_Finalize() the main process will read the resulting trace file and print statistics about the message exchanges: for each pair of processes and each burst of message exchanges, the average offset between the two processes is given. Ideally these offsets will be close to zero, so at the end the pair of processes with the highest absolute clock offset between sender and receiver will be printed: maximum clock offset during run:

```
1 <-> 2 374.738ns (latency 6.752us)
```

to produce graph showing trace timing, run: `gnuplot timertest.gnuplot`





## 5.2. CHOOSING A TIMER

---

If the value is much smaller than the message latency, then clock correction worked well throughout the whole program run and can be trusted to accurately time individual messages.

Running the test program for a short interval is useful to test whether the NTP-like message exchange works in principle, but to get realistic results you have to run the test for several minutes. If a timer is used which is synchronized within a node, then you should run with one process per node because ITC would use the same clock correction for all processes on the same node anyway. Running with multiple processes per node in this case would only be useful to check whether the timer really is synchronized within the node.

To better understand the behaviour of large runs, several data files and one command file for gnuplot are generated. Running gnuplot as indicated above will produce several graphs:

**Application Run** a graph connecting the offsets derived from the application's message exchanges with straight lines: this shows whether the deviation from the expected zero offset is linear or not; this can be very noisy because outliers are not removed

**Clock Transformation** a graph showing the clock samples that ITC itself took at the application start, end and in `VT_timesync()` and what the transformation from local clock ticks to global clock ticks looks like.

**Interpolation Error** a graph comparing a simple linear interpolation of ITC's sample data against the non-linear constrained spline interpolation: at each sample point, the absolute delta between measured time offset and the corresponding interpolated value is shown above the x-axis (for linear interpolation) and below (for splines)

**raw clock samples** for the first three message exchanges of each process the raw clock samples taken by ITC are shown in two different ways: all samples and just those actually used by ITC after removing outliers. In these displays the height of the error bars corresponds to the round-trip time of each sample measured on the master. If communication works reliably, most samples should have the same round-trip time.

Note that the graphs use different coordinate systems: the first one uses global time for both axis, the latter two have local time on the x-axis and a delta in global time on the y-axis. So although the same error will show up in all of them, in one graph it will be as a deviation f.i. below the x-axis and in the other above it.

Also, the later two graphs are only useful if ITC really uses non-linear interpolation which is not the case if all intermediate clock samples are skipped: although the test program causes a clock synchronization before each message exchange by calling `VT_timesync()`, at the same time it tells ITC to not use those results and thus simulates a default application run where synchronization is only done at the start and end.

This can be overridden by setting the `TIMER-SKIP` configuration option or `VT_TIMER_SKIP` environment variable to a small integer value: it chooses how often the result of a `VT_timesync()` is ignored before using a sample for non-linear clock correction. The skipped samples serve as checks that the interpolation is sound.

In the following figures the test program was run using the CPU timer source, with a total runtime of 10 minutes and skipping 5 samples:

```
bash$ VT_TIMER_SKIP=5 VT_TIMER=CPU mpirun -np 4 timertest 600
...
[0 (node0)] performance: 115750510 calls in 5.000s wall
    clock time = 43.197ns/call = 23149574 calls/s
...
0. recording messages 0 <-> 1...
0. recording messages 0 <-> 2...
0. recording messages 0 <-> 3...
0. recording messages 1 <-> 2...
0. recording messages 1 <-> 3...
0. recording messages 2 <-> 3...
1. recording messages 0 <-> 1...
...
maximum clock offset during run:
    0 <-> 1 -1.031us (latency 6.756us)
```

The application run in figure 5.1 shows that in general ITC managed to keep the test results inside a range of plus/minus 1us although it did not use all the information collected with `VT_timesync()`. The clock transformation function in figure 5.2 is non-linear for all three child processes and interpolates the intermediate samples well. Using a linear interpolation between start and end would have led to deviations in the middle of more than 16us. Also, the constrained spline interpolation is superior compared to a simple linear interpolation between the sample points (figure 5.3).




Figure 5.1: CPU timer: application run with non-linear clock correction.




Figure 5.2: CPU timer: clock transformation and the sample points it is based on.

### 5.2.1 gettimeofday/\_ftime

`gettimeofday` is the default timer on Linux\* with `_ftime` being the equivalent on Microsoft\* Windows\*. Its API limits the clock resolution to 1us, but depending on which timer the OS actually uses the clock resolution may be much lower (`_ftime` usually shows a resolution of only 1 millisecond). It is implemented as a system call, therefore it has a higher overhead than other timers.

In theory the advantage of this call is that the OS can make better use of the available hardware, so this timer should be stable over time even if NTP is not running. However, figure 5.4 shows that in practice at least on that system quite a high deviation between different nodes occurred during the run.

If NTP is running, then the clock of each node might be modified by the NTP daemon in a non-linear way. NTP should not cause jumps, only accelerate or slow down the system time. However, even decreasing system time stamps have been observed on some systems. This may or may not have been due to NTP.

Due to the clock synchronization at runtime enabling NTP did not make the result worse than it is without NTP (figure 5.5). However, NTP alone without the additional intermediate synchronization would have led to deviations of nearly 70us.

So the recommendation is to enable NTP, but intermediate clock synchronization by ITC is still needed to achieve good results.




Figure 5.3: CPU timer: error with linear (above x-axis) and non-linear interpolation (below).

## 5.2.2 QueryPerformanceCounter

On Microsoft\* Windows\* the Intel® Trace Collector uses QueryPerformanceCounter as the default timer. As a system function it comes with the same side-effects as `_ftime` but has a higher resolution of around 1 microsecond.

## 5.2.3 CPU Cycle Counter (TSC/ITC)

This is a high-resolution counter inside the CPU which counts CPU cycles. This counter is called Timer Stamp Counter (TSC) on x86/Intel® 64 architectures and Interval Time Counter (ITC) on Itanium®. It can be read via an assembler instruction, so the overhead is much lower than `gettimeofday()`. On the other hand, these counters were never meant to measure long time intervals, so the clock speed also varies a lot, as seen earlier in figure 5.2.

Additional complications are:

**multi-CPU machines** The counter is CPU specific, so if threads migrate from one CPU to another the clock that ITC reads might jump arbitrarily. ITC cannot compensate this as it would have to identify the current CPU and read the register in one atomic operation, which cannot be done from user space without considerable overhead.

CPU cycle counters might still be useful on multi-CPU systems: Linux tries to set the registers of all CPUs to the same value when it boots. If all CPUs receive their clock pulse from the same source their counters do not drift apart later on and it does not matter on which CPU a thread reads the CPU register, the value will be the same one each.




Figure 5.4: gettimeofday() without NTP.

This problem could be addressed by locking threads onto a specific CPU, but that could have an adverse effect on application performance and thus is not supported by ITC itself. If done by the application or some other component, then care has to be taken that all threads in a process run on the same CPU, including those created by ITC itself (see MEM-FLUSH-BLOCKS and “Recording OS Counters”, 3.10). If the application already is single-threaded, then the additional ITC threads could be disabled to avoid this complication.

**frequency scaling** Power-saving mode might lead to a change in the frequency of the cycle count register during the run and thus a non-linear clock drift. Machines meant for HPC probably do not support frequency scaling or will not enter power-saving mode. Even then, on Intel CPUs, TSC often continues to run at the original frequency.

### 5.2.4 MPI\_Wtime()

This timer is provided by the MPI implementation. In general this is simply a wrapper around gettimeofday() and then using it instead of gettimeofday() only has disadvantages: with gettimeofday() ITC knows that processes running on the same node share the same clock and thus does not synchronize between them. The same information cannot be obtained via the MPI API and thus ITC is conservative and assumes that clock synchronization is needed. This can be overridden with the [SYNCED-HOST](#) configuration option. Another disadvantage is increased overhead and potentially implementation errors in MPI (as seen in some versions of MPICH\*).

If the MPI has access to a better timer source (for example a global clock in the underlying communication hardware), then using this timer would be advantageous.




Figure 5.5: `gettimeofday()` with NTP.

### 5.2.5 High Precision Event Timers (HPET)

This is a hardware timer source designed by Intel as replacement for the real time clock (RTC) hardware commonly found in PC boards. Availability and support for it in BIOS and OS is still very limited, therefore ITC does not support it yet.

### 5.2.6 POSIX `clock_gettime`

This is another API specified by the Single Unix Specification and POSIX. It offers a monotonic system clock which is not affected (for good or bad) by NTP, but the current implementation in Linux/glibc does not provide better timing via this API than through `gettimeofday()`. ITC currently does not support this API.

## Chapter 6

# Tracing of Distributed Applications

Processes in non-MPI applications or systems are created and communicate using non-standard and varying methods. The communication may be slow or unsuitable for ITC's communication patterns. Therefore a special version of the ITC library was developed that neither relies on MPI nor on the application's communication, but rather implements its own communication layer using TCP/IP.

This chapter describes the design, implementation and usage of ITC for distributed applications. This is work in progress, so this chapter also contains comments about possible extensions and feedback is welcome.

## 6.1 Design

The following conditions have to be met by the application:

- The application handles startup and termination of all processes itself. Both startup with a fixed number of processes and dynamic spawning of processes is supported, but spawning processes is an expensive operation and should not be done too frequently.
- For a reliable startup, the application has to gather a short string from every process in one place to bootstrap the TCP/IP communication in ITC. Alternatively one process is started first and its string is passed to the others. In this case you can assume that the string is always the same for each program run, but this is less reliable because the string encodes a dynamically chosen port which may change.
- Map the hostname to an IP address that all processes can connect to. Note that this is not the case if `/etc/hosts` lists the hostname as alias for `127.0.0.1` and processes are started on different hosts. As a workaround for that case the hostname is sent to other processes, which then requires a working name lookup on their host systems.

ITC for distributed applications consists of a special library (`libVTcs`) that is linked into the application's processes and the `VTserver` executable, which connects to all processes and coordinates the trace file writing. Linking with `libVTcs` is required to keep the overhead of logging events as small as possible, while `VTserver` can be run easily in a different process.

Alternatively, the functionality of the `VTserver` can be accomplished with another API call by one of the processes.



## 6.2 Using VTserver

This is how the application starts, collects trace data and terminates:

1. The application initializes itself and its communication.
2. The application initializes communication between VTserver and processes.
3. Trace data is collected locally by each process.
4. VT data collection is finalized, which moves the data from the processes to the VT server, where it is written into a file.
5. The application terminates.

The application may iterate several times over points 2 till 4. Looping over 3 and the trace data collection part of 4 are not supported at the moment, because:

- it requires a more complex communication between the application and VTserver
- the startup time for 2 is expected to be sufficiently small
- reusing the existing communication would only work well if the selection of active processes does not change

If the startup time turns out to be unacceptably high, then the protocol between application and ITC could be revised to support reusing the established communication channels.

### 6.2.1 Initialize and Finalize

The application has to bootstrap the communication between the VTserver and its clients. This is done as follows:

1. The application server initiates its processes.
2. Each process calls `VT_clientinit()`.
3. `VT_clientinit()` allocates a port for TCP/IP communication with the VTserver or other clients and generates a string which identifies the machine and this port.
4. Each process gets its own string as result of `VT_clientinit()`.
5. The application collects these strings in one place and calls VTserver with all strings as soon as all clients are ready. VT configuration is given to the VTserver as file or via command line options.
6. Each process calls `VT_initialize()` to actually establish communication.
7. The VTserver establishes communication with the processes, then waits for them to finalize the trace data collection.
8. Trace data collection is finalized when all processes have called `VT_finalize()`.
9. Once the VTserver has written the trace file, it quits with a return code indicating success or failure.





### 6.3. RUNNING WITHOUT VTSERVER

---

Some of the VT API calls may block, especially `VT_initialize()`. Execute them in a separate thread if the process wants to continue. These pending calls can be aborted with `VT_abort()`, for example if another process failed to initialize trace data collection. This failure has to be communicated by the application itself and it also has to terminate the VTserver by sending it a kill signal, because it cannot be guaranteed that all processes and the VTserver will detect all failures that might prevent establishing the communication.

## 6.3 Running without VTserver

Instead of starting VTserver as rank #0 with the contact strings of all application processes, one application process can take over that role. It becomes rank #0 and calls `VT_serverinit()` with the information normally given to VTserver. This changes the application startup only slightly.

A more fundamental change is supported by first starting one process with rank #0 as server, then taking its contact string and passing it to the other processes. These processes then give this string as the initial value of the contact parameter in `VT_clientinit()`. To distinguish this kind of startup from the dynamic spawning of process described in the next section, the prefix “S” needs to be added by the application before calling `VT_clientinit()`. An example where this kind of startup is useful is a process which preforks several child processes to do some work.

In both cases it may be useful to note that the command line arguments previously passed to VTserver can be given in the `argc/argv` array as described in the documentation of `VT_initialize()`.

## 6.4 Spawning Processes

Spawning new processes is expensive, because it involves setting up TCP communication, clock synchronization, configuration broadcasting, amongst others. It's flexibility is also restricted because it needs to map the new processes into the model of “communicators” that provide the context for all communication events. This model follows the one used in MPI and implies that only processes inside the same communicator can communicate at all.

For spawned processes, the following model is currently supported: one of the existing processes starts one or more new processes. These processes need to know the contact string of the spawning process and call `VT_clientinit()` with that information; in contrast to the startup model from the previous section, no prefix is used. Then while all spawned processes are inside `VT_clientinit()`, the spawning process calls `VT_attach()` which does all the work required to connect with the new processes.

The results of this operation are:

- a new `VT_COMM_WORLD` which contains all of the spawned processes, but not the spawning process
- a communicator which contains the spawning process and the spawned ones; the spawning process gets it as result from `VT_attach()` and the spawned processes by calling `VT_get_parent()`

The first of these communicators can be used to log communication among the spawned processes, the second for communication with their parent. There's currently no way to log communication with other processes, even if the parent has a communicator that includes them.



## 6.5 Tracing Events

Once a process' call to `VT_initialize()` has completed successfully it can start calling VT API functions that log events. These events will be associated with a time stamp generated by ITC and with the thread that calls the function.

Should the need arise then VT API functions could be provided that allow one thread to log events from several different sources instead of just itself.

Event types supported at the moment are those also provided in the normal ITC, like state changes (`VT_enter()`, `VT_leave()`) and sending and receiving of data (`VT_log_sendmsg()`, `VT_log_recvmsg()`). The resulting trace file is in a format that can be loaded and analyzed with the standard ITA tool.

## 6.6 Usage

Executables in the application are linked with `-IVTcs` and the same additional parameters as listed in section 3.3. It is possible to have processes implemented in different languages, as long as they use the same version of the `libVTcs`.

The VTserver has the following synopsis:

```
VTserver <contact infos> [config options]
```

Each contact info is guaranteed to be one word and their order on the command line is irrelevant. The config options can be specified on the command line by adding the prefix `--` and listing its arguments after the keyword. This is an example for contacting two processes and writing into the file `"example.stf"` in STF format:

```
VTserver <contact1> <contact2> --logfile-name example.stf
```

All options can be given as environment variables. The format of the config file and environment variables are described in more detail in the chapter about `VT_CONFIG`.

## 6.7 Signals

`libVTcs` uses the same techniques as fail-safe MPI tracing (3.1.7) to handle failures inside the application, therefore it will generate a trace even if the application segfaults or is aborted with CTRL-C.

When only one process runs into a problem, then `libVTcs` tries to notify the other processes, which then should stop their normal work and enter trace file writing mode. If this fails and the application hangs, then it might still be possible to generate a trace by sending a SIGINT to all processes manually.

## 6.8 Examples

There are two examples using MPI as means of communication and process handling. But as they are not linked against the normal ITC library, tracing of MPI has to be done with VT API calls.



## 6.8. EXAMPLES

---

`clientserver.c` is a full-blown example that simulates and handles various error conditions. It uses threads and `fork/exec` to run API functions resp. VTserver concurrently. `simplecs.c` is a stripped down version that is easier to read, but does not check for errors.

The dynamic spawning of processes is demonstrated by `forkcs.c`. It first initializes one process as server with no clients, then forks to create new processes and connects to them with `VT_attach()`. This is repeated recursively. Communication is done via pipes and logged in the new communicators.

`forkcs2.c` is a variation of the previous example which also uses `fork` and pipes, but creates the additional processes at the beginning without relying on dynamic spawning.



## Chapter 7

# Structured Tracefile Format

### 7.1 Introduction

The Structured Trace File Format (STF) is a format that stores data in several physical files by default. This chapter explains the motivation for this change and provides the technical background to configure and work with the new format. It is safe to skip over this chapter because all configuration options that control writing of STF have reasonable default values.

The development of STF was motivated by the observation that the conventional approach of handling trace data in a single trace file is not suitable for large applications or systems, where the trace file can quickly grow into the tens of Gigabytes range. On the display side, such huge amounts of data cannot be squeezed into one display at once. Provide mechanisms to start at a coarser level of display and then resolve the display into more detailed information. Also, the ability to request and inspect only parts of the data becomes essential with the amount of trace data growing.

These requirements necessitate a more powerful data organization than the previous ITA tracefile format can provide. In response to this, the Structured Tracefile Format (STF) has been developed. The aim of the STF is to provide a file format which:

- can arbitrarily be partitioned into several files, each one containing a specific subset of the data
- allows fast random access and easy extraction of data
- is extensible, portable, and upward compatible
- is clearly defined and structured
- can efficiently exploit parallelism for reading and writing
- is as compact as possible

The traditional tracefile format is only suitable for small applications, and cannot efficiently be written in parallel. Also, it was designed for reading the entire file at once, rather than for extracting arbitrary data. The structured tracefile implements these new requirements, with the ability to store large amounts of data in a more compact form.




Figure 7.1: STF components

## 7.2 STF Components

A structured tracefile actually consists of a number of files as shown in the figure 7.1. Depending on the organization of actual files, the following component files will be written, with `<trace>` being the tracefile name that can be automatically determined or set by the `LOGFILE-NAME` directive:

- one index file with the name `<trace>.stf`
- one record declaration file with the name `<trace>.stf.dcl`
- one statistics file with the name `<trace>.stf.sts`
- one message file with the name `<trace>.stf.msg`
- one global operation file with the name `<trace>.stf.gop`
- one or more process files with the name `<trace>.stf.pr.<index>`
- for the above three kinds of files, one anchor file each with the added extension `.anc`

The records for routine entry/exit and counters are contained in the process files. The anchor files are used by ITA to “fast-forward” within the record files; they can be deleted, but that may result in slower operation of ITA.

Make sure that you use different names for traces from different runs; otherwise you will experience difficulties in identifying which process files belong to an index file, and which ones are left over from a previous run. To catch all component files, use the `stftool` with the `--remove` option to delete a STF file, or put the files into single-file STF format for transmission or archival with the `stftool --convert` option (see section 7.4.1).

The number of actual process files will depend on the setting of the `STF-USE-HW-STRUCTURE` and `STF-PROCS-PER-FILE` configuration options described below.

## 7.3 Single-File STF

As a new option in ITC, the trace data can be saved in the single-file STF format. This format is selected by specifying the [LOGFILE-FORMAT STFSINGLE](#) configuration directive, and it causes all the component files of an STF trace to be combined into one file with the extension `.single.stf`. The logical structure is preserved. The drawback of the single-file STF format is that no I/O parallelism can be exploited when writing the tracefile.

Reading it for analysis with ITA is only marginally slower than the normal STF format, unless the operating system imposes a performance penalty on parallel read accesses to the same file.

## 7.4 Configuring STF

The STF behavior which can be configured using directives in the ITC configuration file or the equivalent environment variables are also described in [section 9](#).

To determine the file layout, the following options can be used:

**STF-USE-HW-STRUCTURE** will save the local events for all processes running on the same node into one process file

**STF-PROCS-PER-FILE** `<number>` limits the number of processes whose events can be written in a single process file

**STF-CHUNKSIZE** `<bytes>` determines at which intervals the anchors are set

All of these options are explained in more detail in the [VT.CONFIG](#) chapter.

### 7.4.1 Structured Trace File Manipulation

#### Synopsis

```
stftool <input file> <config options>
--help
--version
```

#### Description

The `stftool` utility program reads a structured trace file (STF) in normal or single-file format. It can perform various operations with this file:

- extract all or a subset of the trace data (default)
- convert the file format without modifying the content (`--convert`)
- list the components of the file (`--print-files`)
- remove all components (`--remove`)
- rename or move the file (`--move`)
- list statistics (`--print-statistics`)

The output and behaviour of `stftool` is configured similarly to ITC: with a config file, environment variables and command line options. The environment variable [VT.CONFIG](#) can be set to the name of a ITC configuration file. If the file exists and is readable, then it is parsed first. Its settings are overridden with environment variables, which in turn are overridden by config options on the command line.



All config options can be specified on the command line by adding the prefix "--" and listing its arguments after the keyword. The output format is derived automatically from the suffix of the output file. You can write to stdout by using "-" as filename; this defaults to writing ASCII VTF.

These are examples of converting the entire file into different formats:

```
stftool example.stf --convert example.avt # ASCII
stftool example.stf --convert -          # ASCII to stdout
stftool example.stf --convert - --logfile-format SINGLESTF |
gzip -c >example.single.stf.gz          # gzipped single-file STF
```

Without the --convert switch one can extract certain parts, but only write VTF:

```
stftool example.stf --request 1s:5s
--logfile-name example_1s5s.avt # extract interval as ASCII
```

All options can be given as environment variables. The format of the config file and environment variables are described in more detail in the documentation for [VT.CONFIG](#).

## Supported Directives

### --convert

**Syntax:** [<filename>]

**Default:** off

Converts the entire file into the file format specified with --logfile-format or the filename suffix. Options that normally select a subset of the trace data are ignored when this low-level conversion is done. Without this flag writing is restricted to ASCII format, while this flag can also be used to copy any kind of STF trace.

### --move

**Syntax:** [<file/dirname>]

**Default:** off

Moves the given file without otherwise changing it. The target can be a directory.

### --remove

**Syntax:**

**Default:** off

Removes the given file and all of its components.

### --print-files

**Syntax:**

**Default:** off

List all components that are part of the given STF file, including their size. This is similar to "ls -l", but also works with single-file STF.

### --print-statistics

**Syntax:**

**Default:** off

Prints the precomputed statistics of the input file to stdout.

### --print-threads

**Syntax:**

**Default:** off

Prints information about each native thread that was encountered by ITC when generating the trace.

### --print-errors

**Syntax:**

**Default:** off

Prints the errors that were found in the application.

### --dump

**Syntax:**





## 7.4. CONFIGURING STF

---

**Default:** off

This is a shortcut for "--logfile-name -" and "--logfile-format ASCII", that is, it prints the trace data to stdout.

### --request

**Syntax:** "<type>", <thread triplets>, <categories>, <window>

This option restricts the data that is written into the new trace to that which matches the arguments. If a window is given (in the form <timespec>:<timespec> with at least one unit descriptor), data is restricted to this time interval. It has the usual format of a time value, with one exception: the unit for seconds "s" is not optional to distinguish it from a thread triplet; in other words, use "10s" instead of just "10". The <type> can be any kind of string in single or double quotation marks, but it has to uniquely identify the kind of data. Valid <categories> are FUNCTIONS, SCOPES, FILEIO, COUNTERS, MESSAGES, COLLOPS, ERRORS and REQUESTS.

All of the arguments are optional and default to all threads, all categories and the whole time interval. They can be separated by commas or spaces and it is possible to mix them as desired. This option can be used more than once and then data matching any request is written.

### --ticks

**Syntax:**

**Default:** off

Setting this option to 'on' lets stftool interpret all timestamps as ticks (rather than seconds, milliseconds and so on). Given time values are converted into seconds and then truncated (floor).

The clock ticks are based on the nominal clock period specified by the CLKPERIOD header, just as the time stamps printed by the stftool for events.

### --logfile-name

**Syntax:** <file name>

Specifies the name for the tracefile containing all the trace data. Can be an absolute or relative pathname; in the latter case, it is interpreted relative to the log prefix (if set) or the current working directory of the process writing it.

If unspecified, then the name is the name of the program plus ".avt" for ASCII, ".stf" for STF and ".single.stf" for single STF tracefiles. If one of these suffices is used, then they also determine the logfile format, unless the format is specified explicitly.

In the stftool the name has to be specified explicitly, either by using this option or as argument of the --convert or --move switch.

### --logfile-format

**Syntax:** [ASCII|STF|STFSINGLE|SINGLESTF]

**Default:** STF

Specifies the format of the tracefile. ASCII is the traditional Vampir file format where all trace data is written into one file. It is human-readable.

The Structured Trace File (STF) is a binary format which supports storage of trace data in several files and allows ITA to analyze the data without loading all of it, so it is more scalable. Writing it is only supported by ITC at the moment.

One trace in STF format consists of several different files which are referenced by one index file (.stf). The advantage is that different processes can write their data in parallel (see [STF-PROCS-PER-FILE](#), [STF-USE-HW-STRUCTURE](#)). SINGLESTF rolls all of these files into one (.single.stf), which can be read without unpacking them again. However, this format does not support distributed writing, so for large program runs with many processes the generic STF format is better.

### --extended-vtf

**Syntax:**

**Default:** off in ITC, on in stftool

Several events can only be stored in STF, but not in VTF. ITC libraries default to writing valid VTF trace files and thus skip these events. This option enables writing of non-standard VTF records in ASCII mode that ITA would complain about. In the stftool the default is to write these extended records, because the output is more likely to be parsed by scripts rather than ITA.

**--matched-vtf****Syntax:****Default:** off

When converting from STF to ASCII-VTF communication records are usually split up into conventional VTF records. If this option is enabled, an extended format is written, which puts all information about the communication into a single line.

**--verbose****Syntax:** [on|off|<level>]**Default:** on

Enables or disables additional output on stderr. <level> is a positive number, with larger numbers enabling more output:

- 0 (= off) disables all output
- 1 (= on) enables only one final message about generating the result
- 2 enables general progress reports by the main process
- 3 enables detailed progress reports by the main process
- 4 the same, but for all processes (if multiple processes are used at all)

Levels larger than 2 may contain output that only makes sense to the developers of ITC.

**SEE ALSO**

[VT\\_CONFIG\(3\)](#)

## 7.4.2 Expanded ASCII output of STF files

**Synopsis**

```
xstftool <STF file> [stftool options]
```

Valid options are those that work together with "stftool --dump", the most important ones being:

- --request: extract a subset of the data
- --matched-vtf: put information about complex events like messages and collective operations into one line

**Description**

The xstftool is a simple wrapper around the stftool and the expandvtlog.pl Perl script which tells the stftool to dump a given Structured Trace Format (STF) file in ASCII format and uses the script as a filter to make the output more readable.

It is intended to be used for doing custom analysis of trace data with scripts that parse the output to extract information not provided by the existing tools, or for situations where a few shell commands provide the desired information more quickly than a graphical analysis tool.

**Output**

The output has the format of the ASCII Vampir Trace Format (VTF), but entities like function names are not represented by integer numbers that cannot be understood without remembering their definitions, but rather inserted into each record. The CPU numbers that encode process and thread ranks resp. groups are also expanded.



### Examples

The following examples compare the output of "stftool --dump" with the expanded output of "xstftool":

- definition of a group

```
DEFGROUP 2147942402 "All_Processes" NMEMBS 2 2147483649 2147483650
DEFGROUP All_Processes NMEMBS 2 "Process_0" "Process_2"
```

- a counter sample on thread 2 of the first process

```
8629175798 SAMP CPU 131074 DEF 6 UINT 8 3897889661
8629175798 SAMP CPU 2:1 DEF "PERF_DATA:PAPI_TOT_INS" UINT 8 3897889661
```



## Chapter 8

# User-level Instrumentation with the API

### 8.1 The ITC API

The ITC library provides the user with a number of routines that control the profiling library and record user-defined activities, define groups of processes, define performance counters and record their values. Header files with the necessary parameter, macro and function declarations are provided in the include directory: VT.h for ANSI C and C++ and VT.inc for Fortran 77 and Fortran 90. It is strongly recommended to include these header files if any ITC API routines are to be called.

#### **`#define VT_VERSION`**

API version constant.

It is incremented each time the API changes, even if the change does not break compatibility with the existing API. It can be used to determine at compile time how to call the API, like this:

```
#if VT_VERSION > 4000
    do something
#else
    do something different
#endif
```

`VT_version()` provides the same information at runtime.

To check whether the current revision of the API is still compatible with the revision of the API that the application was written against, compare against both `VT_VERSION` and `VT_VERSION_COMPATIBILITY`, as shown below.

#### **`#define VT_VERSION_COMPATIBILITY`**

Oldest API definition which is still compatible with the current one.



This is set to the current version each time an API change can break programs written for the previous API. For example, a program written for `VT_VERSION` 2090 will work with API 3000 if `VT_VERSION_COMPATIBILITY` remained at 2090. It may even work without modifications when `VT_VERSION_COMPATIBILITY` was increased to 3000, but this cannot be determined automatically and will require a source code review.

Here is a usage example:

```
#define APP_VT_VERSION 1000 // API version used by APP
#ifdef VT_VERSION_COMPATIBILITY > APP_EXPECTED_VT_VERSION
# error "VT.h is no longer compatible with APP's usage of the API"
#endif
#ifdef VT_VERSION < APP_EXPECTED_VT_VERSION
# error "VT.h is not recent enough for APP"
#endif
```

### ***enum* \_VT\_ErrorCode**

error codes returned by ITC API.

#### **Enumeration values:**

- VT\_OK** OK.
- VT\_ERR\_NOLICENSE** no valid license found.
- VT\_ERR\_NOTIMPLEMENTED** Not (yet?) implemented.
- VT\_ERR\_NOTINITIALIZED** Not initialised.
- VT\_ERR\_BADREQUEST** Invalid request type.
- VT\_ERR\_BADSYMBOLID** Wrong symbol id.
- VT\_ERR\_BADSCLID** wrong SCL id.
- VT\_ERR\_BADSCL** wrong SCL.
- VT\_ERR\_BADFORMAT** wrong format.
- VT\_ERR\_BADKIND** Wrong kind found.
- VT\_ERR\_NOMEMORY** Could not get memory.
- VT\_ERR\_BADFILE** Error while handling file.
- VT\_ERR\_FLUSH** Error while flushing.
- VT\_ERR\_BADARG** wrong argument.
- VT\_ERR\_NOTTHREADS** no worker threads.
- VT\_ERR\_BADINDEX** wrong thread index.
- VT\_ERR\_COMM** communication error.
- VT\_ERR\_INVT** ITC API called while inside an ITC function.
- VT\_ERR\_IGNORE** non-fatal error code.

Suppose you instrumented your C source code for the API with `VT_VERSION` equal to 3100. Then you could add the following code fragment to detect incompatible changes in the API:

```
#include <VT.h>
#if VT_VERSION_COMPATIBILITY > 3100
# error ITC API is no longer compatible with our calls
#endif
```

Of course, breaking compatibility that way will be avoided at all costs. Beware of comparing against a fixed number and not `VT_VERSION`, because `VT_VERSION` will always be greater or equal `VT_VERSION_COMPATIBILITY`.



To make the instrumentation work again after such a change, you can either just update the instrumentation to accommodate for the change or even provide different instrumentation that is chosen by the C preprocessor based on the value of `VT_VERSION`.

## 8.2 Initialization, Termination and Control

ITC is automatically initialized within the execution of the `MPI_Init()` routine. During the execution of the `MPI_Finalize()` routine, the trace data collected in memory or in temporary files is consolidated and written into the permanent trace file(s), and ITC is terminated. Thus, it is an error to call ITC API functions before `MPI_Init()` has been executed or after `MPI_Finalize()` has returned.

In non-MPI applications it may be necessary to start and stop ITC explicitly. These calls also help to write programs and libraries that use VT without depending on MPI.

### ***int VT\_initialize (int \* argc, char \*\*\* argv)***

Initialize ITC and underlying communication.

`VT_initialize()`, `VT_getrank()`, `VT_finalize()` can be used to write applications or libraries which work both with and without MPI, depending on whether they are linked with `libVT.a` plus MPI or with `libVTcs.a` (distributed tracing) and no MPI.

If the MPI that ITC was compiled for provides `MPI_Init_thread()`, then `VT_init()` will call `MPI_Init_thread()` with the parameter *required* set to `MPI_THREAD_FUNNELED`. This is sufficient to initialize multithreaded applications where only the main thread calls MPI. If your application requires a higher thread level, then either use `MPI_Init_thread()` instead of `VT_init()` or (if `VT_init()` is called e.g. by your runtime environment) set the environment variable `VT_THREAD_LEVEL` to a value of 0 till 3 to choose thread levels `MPI_THREAD_SINGLE` till `MPI_THREAD_MULTIPLE`.

It is not an error to call `VT_initialize()` twice or after a `MPI_Init()`.

In a MPI application written in C the program's parameters must be passed, because the underlying MPI might require them. Otherwise they are optional and 0 resp. a NULL pointer may be used. If parameters are passed, then the number of parameters and the array itself may be modified, either by MPI or ITC itself.

ITC assumes that `(*argv)[0]` is the executable's name and uses this string to find the executable and as the basename for the default logfile name. Other parameters are ignored unless there is the special `"-tracecollector-args"` parameters: then all following parameters are interpreted as configuration options, written with a double hyphen as prefix and a hyphen instead of underscores (e.g. `-tracecollector-args -logfile-format BINARY -logfile-prefix /tmp`). These parameters are then removed from the `argv` array, but not freed. To continue with the program's normal parameters, `-tracecollector-args-end` may be used. There may be more than one block of ITC arguments on the command line.

### **Fortran**

```
VTINIT( ierr )
```

### **Parameters:**

***argc*** a pointer to the number of command line arguments

***argv*** a pointer to the program's command line arguments

### **Returns:**

error code

***int VT\_finalize (void)***

Finalize ITC and underlying communication.

It is not an error to call `VT_finalize()` twice or after a `MPI_Finalize()`.

**Fortran**

```
VTFINI( ierr )
```

**Returns:**

error code

***int VT\_getrank (int \* rank)***

Get process index (same as MPI rank within `MPI_COMM_WORLD`).

Beware that this number is not unique in applications with dynamic process spawning.

**Fortran**

```
VTGETRANK( rank, ierr )
```

**Return values:**

***rank*** process index is stored here

**Returns:**

error code

The following functions control the tracing of threads in a multithreaded application.

***int VT\_registerthread (int thindex)***

Registers a new thread with ITC under the given number.

Threads are numbered starting from 0, which is always the thread that has called `VT_initialize()` resp. `MPI_Init()`. The call to `VT_registerthread()` is optional: a thread that uses ITC without having called `VT_registerthread()` is automatically assigned the lowest free index. If a thread terminates, then its index becomes available again and might be reused for another thread.

Calling `VT_registerthread()` when the thread has been assigned an index already is an error, unless the argument of `VT_registerthread()` is equal to this index. The thread is not (re)registered in case of an error.

**Fortran**

```
VTREGISTERTHREAD( thindex, ierr )
```

**Parameters:**

***thindex*** thread number, only used if  $\geq 0$

**Returns:**

error code:

- `VT_ERR_BADINDEX` - thread index is currently assigned to another thread
- `VT_ERR_BADARG` - thread has been assigned a different index already
- `VT_ERR_NOTINITIALIZED` - ITC wasn't initialized yet

***int VT\_registernamed (const char \* threadname, int thindex)***

Registers a new thread with ITC under the given number and name.

Threads with the same number cannot have different names. If you try that, the thread uses the number, but not the new name.





## 8.2. INITIALIZATION, TERMINATION AND CONTROL

---

Trying to register a thread twice with different names or numbers is an error. One can add a name to an already registered thread with `VT_registerthread( "new name", -1 )` if no name has been set before.

**Parameters:**

***threadname*** desired name of the thread, or NULL/empty string if no name wanted

***thindex*** desired thread number, pass negative number to let ITC pick a number

**Returns:**

error code, see `VT_registerthread()`

***int VT\_getthrank (int \* thrank)***

Get thread index within process.

Either assigned automatically by ITC or manually with `VT_registerthread()`.

**Fortran**

VTGETTHRANK( thrank, ierr )

**Return values:**

***thrank*** thread index within current thread is stored here

**Returns:**

error code

The recording of performance data can be controlled on a per-process basis by calls to the `VT_traceon()` and `VT_traceoff()` routines: a thread calling `VT_traceoff()` will no longer record any state changes, MPI communication or counter events. Tracing can be re-enabled by calling the `VT_traceon()` routine. The collection of statistics data is not affected by calls to these routines. With the API routine `VT_tracestate()` a process can query whether events are currently being recorded.

***void VT\_traceoff (void)***

Turn tracing off for thread if it was enabled, does nothing otherwise.

**Fortran**

VTTTRACEOFF( )

***void VT\_traceon (void)***

Turn tracing on for thread if it was disabled, otherwise do nothing.

Cannot enable tracing if "PROCESS/CLUSTER NO" was applied to the process in the configuration.

**Fortran**

VTTTRACEON( )

***int VT\_tracestate (int \* state)***

Get logging state of current thread.

Set by config options `PROCESS/CLUSTER`, modified by `VT_traceon/off()`.

There are three states:



- 0 = thread is logging
- 1 = thread is currently not logging
- 2 = logging has been turned off completely

Note that different threads within one process may be in state 0 and 1 at the same time because [VT\\_traceon/off\(\)](#) sets the state of the calling thread, but not for the whole process.

State 2 is set via config option "[PROCESS/CLUSTER NO](#)" for the whole process and cannot be changed.

**Fortran**

```
VTTRACESTATE( state, ierr )
```

**Return values:**

**state** is set to current state

**Returns:**

error code

With the ITC configuration mechanisms described in chapter [VT\\_CONFIG](#), the recording of state changes can be controlled per symbol or activity. For any defined symbol, the [VT\\_symstate\(\)](#) routine returns whether data recording for that symbol has been disabled.

***int VT\_symstate (int statehandle, int \* on)***

Get filter state of one state.

Set by config options SYMBOL, ACTIVITY.

Note that a state may be active even if the thread's logging state is "off".

**Fortran**

```
VTSYMSTATE( statehandle, on, ierr )
```

**Parameters:**

**statehandle** result of [VT\\_funcdef\(\)](#) or [VT\\_symdef\(\)](#)

**Return values:**

**on** set to 1 if symbol is active

**Returns:**

error code

ITC minimizes the instrumentation overhead by first storing the recorded trace data locally in each processor's memory and saving it to disk only when the memory buffers are filled up. Calling the [VT\\_flush\(\)](#) routine forces a process to save the in-memory trace data to disk, and mark the duration of this in the trace. After returning, ITC continues normally.

***int VT\_flush (void)***

Flushes all trace records from memory into the flush file.

The location of the flush file is controlled by options in the config file. Flushing will be recorded in the trace file as entering and leaving the state VT\_API:TRACE\_FLUSH with time stamps that indicate the duration of the flushing. Automatic flushing is recorded as VT\_API:AUTO\_FLUSH.

**Fortran**

```
VTFLUSH( ierr )
```

**Returns:**

error code



### 8.3. DEFINING AND RECORDING SOURCE LOCATIONS

---

Refer to section 9 to learn about the [MEM-BLOCKSIZE](#) and [MEM-MAXBLOCKS](#) configuration directives that control ITC's memory usage.

ITC makes its internal clock available to applications, which can be useful to write instrumentation code that works with MPI and non-MPI applications:

#### ***double VT\_timestamp (void)***

Returns an opaque time stamp, or [VT\\_ERR\\_NOTINITIALIZED](#).

In contrast to previous versions this time stamp no longer represents seconds. Use [VT\\_timeofday\(\)](#) for that instead. The result of [VT\\_timestamp\(\)](#) can be copied verbatim and given to other API calls, but nothing else.

#### **Fortran**

```
DOUBLE PRECISION VTSTAMP( )
```

#### ***double VT\_timestart (void)***

Returns point in time in seconds when process started, or [VT\\_ERR\\_NOTINITIALIZED](#).

#### **Fortran**

```
DOUBLE PRECISION VTTIMESTART( )
```

## 8.3 Defining and Recording Source Locations

Source locations can be specified and recorded in two different contexts:

**State changes**, associating a source location with the state change. This is useful to record where a routine has been called, or where a code region begins and ends.

**Communication events**, associating a source location with calls to MPI routines, for example, calls to the send/receive or collective communication and I/O routines.

To minimize instrumentation overhead, locations for the state changes and communication events are referred to by integer location handles that can be defined by calling the new API routine [VT\\_scldef\(\)](#), which will automatically assign a handle. The old API routine [VT\\_locdef\(\)](#) which required the user to assign a handle value has been removed. A source location is a pair of a filename and a line number within that file.

#### ***int VT\_scldef (const char \* file, int line\_nr, int \* sclhandle)***

Allocates a handle for a source code location (SCL).

#### **Fortran**

```
VTSCLDEF( file, line_nr, sclhandle, ierr )
```

#### **Parameters:**

***file*** file name

***line\_nr*** line number in this file, counting from 1



**Return values:**

***sclhandle*** the int it points to is set by ITC

**Returns:**

error code

Some functions require a location handle, but they all accept `VT_NOSCL` instead of a real handle:

***#define VT\_NOSCL***

special SCL handle: no location available.

***int VT\_sclstack (void \* pc, void \* stackframe, int skip, int trace, int \* sclhandle)***

Allocates a handle for a source code location (SCL) handle which refers to the current call stack.

This SCL can then be used in several API calls without having to repeat the stack unwinding each time. Which stack frames are preserved and which are skipped is determined by the `PCTRACE` configuration option, but can be overridden with function parameters.

Special support is available for recording source code locations from inside signal handlers by calling this function with the `pc` and `stackframe` parameters different from `NULL`. Other usages of these special parameters include:

- remembering the stack frame in those API calls of a library that are invoked directly by the application, then at arbitrary points in the library do stack unwinding based on that stack frame to catch just the application code
- defining a source code location ID for a specific program counter value

Here is an example of the usage of this call inside a library which implements a message send:

### 8.3. DEFINING AND RECORDING SOURCE LOCATIONS

---

```
void MySend( struct *msg ) {
    int sclhandle;
    VT_sclstack( NULL, NULL, // we use the default stack unwinding
                1,          // MySend() is called directly by the
                            // application code we want to trace:
                            // skip our own source code, but not
                            // more
                -1,        // default PCTRACE setting for size
                            // of recorded stack
                &sclhandle );
    // if an error occurs, we continue with the sclhandle == VT_NOSCL
    // that VT_sclstack() sets
    VT_enter( funchandle,
             sclhandle );
    VT_log_sendmsg( msg->receiver,
                  msg->count,
                  msg->tag,
                  msg->commid,
                  sclhandle );
    // do the send here
    VT_leave( sclhandle );
}
```

#### Parameters:

**pc** record the source code of this program counter value as the innermost call location, then continue with normal stack unwinding; NULL if only stack unwinding is to be used

**stackframe** start unwinding at this stack frame, NULL for starting with the stack frame of `VT_sclstack()` itself: on IA32 the stack frame is found in the EBP register, on Intel(R) 64 in the RBP register, on Itanium(R) in the BSP register

**skip** -1: get the number of stack frames to skip from the `PCTRACE` configuration option 0: first recorded program counter value after the (optional) pc address is the return address of the initial stack frame >0: skip the given number of return addresses

**trace** -1: get the number of stack frames to record from the `PCTRACE` configuration option 0: do not record any source code locations for the call stack: returns an SCL ID for the pc address if one is given, otherwise returns `VT_NOSCL` immediately >0: the number of stack frames to record

#### Return values:

**schandle** the int it points to is set by ITC to a valid SCL handle in case of success and `VT_NOSCL` otherwise

#### Returns:

error code

ITC automatically records all available information about MPI calls. On some systems, the source location of these calls is automatically recorded. On the remaining systems, the source location of MPI calls can be recorded by calling the `VT_thisloc()` routine immediately before the call to the MPI routine, with no intervening MPI or ITC API calls.

#### *int VT\_thisloc (int sclhandle)*

Set source code location for next activity that is logged by ITC.

After being logged it is reset to the default behaviour again: automatic PC tracing if enabled in the config file and supported or no SCL otherwise.

**Fortran**

VTTHISL( sclhandle, ierr )

**Parameters:****sclhandle** handle defined either with [VT\\_scldef\(\)](#)**Returns:**

error code

## 8.4 Defining and Recording Functions or Regions

ITA can display and analyze general (properly nested) state changes, relating to subroutine calls, entry/exit to/from code regions and other activities occurring in a process. ITA implements a two-level model of states: a state is referred to by an activity name that identifies a group of states, and the state (or symbol) name that references a particular state in that group. For instance, all MPI routines are part of the activity MPI, and each one is identified by its routine name, for instance MPI\_Send for C and MPI\_SEND for Fortran.

The ITC API allows the user to define arbitrary activities and symbols and to record entry and exit to/from them. In order to reduce the instrumentation overhead, symbols are referred to by integer handles that can be managed automatically (using the [VT\\_funcdef\(\)](#) interface) or assigned by the user (using the old [VT\\_symdef\(\)](#) routine). All activities and symbols are defined by each process that uses them, but it is no longer necessary to define them consistently on all processes (see [UNIFY-SYMBOLS](#)).

Optionally, information about source locations can be recorded for state enter and exit events by passing a non-null location handle to the [VT\\_enter\(\)/VT\\_leave\(\)](#) or [VT\\_begin\(\)/VT\\_endl\(\)](#) routines.

### 8.4.1 New Interface

To simplify the use of user-defined states, a new interface has been introduced for ITC. It manages the symbol handles automatically, freeing the user from the task of assigning and keeping track of symbol handles, and has a reduced number of arguments. Furthermore, the performance of the new routines has been optimized, reducing the overhead of recording state changes.

To define a new symbol, first the respective activity needs to have been created by a call to the [VT\\_classdef\(\)](#) routine. A handle for that activity is returned, and with it the symbol can be defined by calling [VT\\_funcdef\(\)](#). The returned symbol handle is passed f.i. to [VT\\_enter\(\)](#) to record a state entry event.

***int VT\_classdef (const char \* classname, int \* classhandle)***

Allocates a handle for a class name.

The *classname* may consist of several components separated by a colon (:). Leading and trailing colons are ignored. Several colons in a row are treated as just one separator.

**Fortran**

VTCLASSDEF( classname, classhandle, ierr )

**Parameters:****classname** name of the class**Return values:****classhandle** the int it points to is set by ITC



**Returns:**

error code

***int VT\_funcdef (const char \* symname, int classhandle, int \* statehandle)***

Allocates a handle for a state.

The *symname* may consist of several components separated by a colon (:). If that's the case, then these become the parent class(es). Leading and trailing colons are ignored. Several colons in a row are treated as just one separator.

This is a replacement for [VT\\_symdef\(\)](#) which doesn't require the application to provide a unique numeric handle.

**Fortran**

VTFUNCDEF( symname, classhandle, statehandle, ierr )

**Parameters:**

***symname*** name of the symbol

***classhandle*** handle for the class this symbol belongs to, created with [VT\\_classdef\(\)](#), or [VT\\_NOCLASS](#), which is an alias for "Application" if the *symname* doesn't contain a class name and ignored otherwise

**Return values:**

***statehandle*** the int it points to is set by ITC

**Returns:**

error code

***#define VT\_NOCLASS***

special value for [VT\\_funcdef\(\)](#): put function into the default class "Application".

### 8.4.2 Old Interface

To define a new symbol, first determine which value has to be used for the symbol handle, and then call the [VT\\_symdef\(\)](#) routine, passing the symbol and activity names, plus the handle value. It is not necessary to define the activity itself. Take care not to use the same handle value for different symbols.

***int VT\_symdef (int statehandle, const char \* symname, const char \* activity)***

Defines the numeric *statehandle* as shortcut for a state.

This function will become obsolete and should not be used for new code. Both *symname* and *activity* may consist of more than one component, separated by a colon (:).

Leading and trailing colons are ignored. Several colons in a row are treated as just one separator.

**Fortran**

VTSYMDEF( code, symname, activity, ierr )

**Parameters:**

***statehandle*** numeric value chosen by the application



***symname*** name of the symbol

***activity*** name of activity this symbol belongs to

**Returns:**

error code

### 8.4.3 State Changes

The following routines take a state handle defined with either the new or old interface. Handles defined with the old interface incur a higher overhead in these functions, because they need to be mapped to the real internal handles. Therefore it is better to use the new interface, so that support for the old interface may eventually be removed.

ITC distinguishes between code regions (marked with [VT\\_begin\(\)/VT\\_end\(\)](#)) and functions (marked with [VT\\_enter\(\)/VT\\_leave\(\)](#)). The difference is only relevant when passing source code locations:

#### ***int VT\_begin (int statehandle)***

Marks the beginning of a region with the name that was assigned to the symbol.

Regions should be used to subdivide a function into different parts or to mark the location where a function is called.

**Notes:**

If automatic tracing of source code locations (aka PC tracing) is supported, then ITC will log the location where [VT\\_begin\(\)](#) is called as source code location for this region and the location where [VT\\_end\(\)](#) is called as SCL for the next part of the calling symbol (which may be a function or another, larger region).

If a SCL has been set with [VT\\_thisloc\(\)](#), then this SCL will be used even if PC tracing is supported.

The functions [VT\\_enter\(\)](#) and [VT\\_leave\(\)](#) have been added that can be used to mark the beginning and end of a function call within the function itself. The difference is that a manual source code location which is given to [VT\\_leave\(\)](#) cannot specify where the function call took place, but rather where the function is left. So currently it has to be ignored until the trace file format can store this additional information.

If PC tracing is enabled, then the [VT\\_leave](#) routine stores the SCL where the instrumented function was called as SCL for the next part of the calling symbol. In other words, it skips the location where the function is left, which would be recorded if [VT\\_end\(\)](#) were used instead.

[VT\\_begin\(\)](#) adds an entry to a stack which can be removed with (and only with) [VT\\_end\(\)](#).

**Fortran**

VTBEGIN( statehandle, ierr )

**Parameters:**

***statehandle*** handle defined either with [VT\\_symdef\(\)](#) or [VT\\_funcdef\(\)](#)

**Returns:**

error code

#### ***int VT\_beginl (int statehandle, int sclhandle)***

Shortcut for [VT\\_thisloc\( sclhandle \); VT\\_begin\( statehandle \)](#).

**Fortran**

VTBEGINL( statehandle, sclhandle, ierr )



***int VT\_end (int statehandle)***

Marks the end of a region.

Has to match a [VT\\_begin\(\)](#). The parameter was used to check this, but this is no longer done to simplify instrumentation; now it is safe to pass a 0 instead of the original state handle.

**Fortran**

```
VTEND( statehandle, ierr )
```

**Parameters:**

**statehandle** obsolete, pass anything you want

**Returns:**

error code

***int VT\_endl (int statehandle, int sclhandle)***

Shortcut for [VT\\_thisloc\( sclhandle \); VT\\_end\( statehandle \)](#).

**Fortran**

```
VTENDL( statehandle, sclhandle, ierr )
```

***int VT\_enter (int statehandle, int sclhandle)***

Mark the beginning of a function.

Usage similar to [VT\\_beginl\(\)](#). See also [VT\\_begin\(\)](#).

**Fortran**

```
VTENTER( statehandle, sclhandle, ierr )
```

**Parameters:**

**statehandle** handle defined either with [VT\\_symdef\(\)](#) or [VT\\_funcdef\(\)](#)

**sclhandle** handle, defined by [VT\\_scldef](#). Use [VT\\_NOSCL](#) if you don't have a specific value.

**Returns:**

error code

***int VT\_leave (int sclhandle)***

Mark the end of a function.

See also [VT\\_begin\(\)](#).

**Fortran**

```
VTLEAVE( sclhandle, ierr )
```

**Parameters:**

**sclhandle** handle, defined by [VT\\_scldef](#). Currently ignored, but is meant to specify the location of exactly where the function was left in the future. Use [VT\\_NOSCL](#) if you don't have a specific value.

**Returns:**

error code

***int VT\_enterstate (const char \* name, int \* statehandle, int \* truncated)***

Defines a state (when invoked the first time) and enters it.



It relies on the caller to provide persistent storage for state handles.

The corresponding call to leave the state again is the normal `VT_leave()`. `VT_leave()` must be called if and only if `VT_enterstate()` returns a zero return code.

```
static int bsend_handle, bsend_truncated;
int bsend_retval;
bsend_retval = VT_enterstate( "MPI:TRANSFER:BSEND",
                             &bsend_handle, &bsend_truncated );
...
if( !bsend_retval ) VT_leave( VT_NOSCL );
```

As demonstrated in this example, one or more colons (:) may be used to specify parent classes of the state, just as in `VT_funcdef()` et.al.

But in contrast to those, `VT_enterstate()` also treats a slash (/) as special and uses it to log states at a varying degree of detail: depending on the value of `DETAILED-STATES` (0 = OFF, 1 = ON, 2, 3...), only the part of the name before the first slash is used (`DETAILED-STATES` 0). For higher values of `DETAILED-STATES` more components of the name are used and the slashes in the part of the name which is used is treated like the class separator (:).

Examples:

- "MPI:TRANSFER/SEND/COPY" + `DETAILED-STATES` 0: "MPI:TRANSFER"
- "MPI:TRANSFER/SEND/COPY" + `DETAILED-STATES` 1: "MPI:TRANSFER:SEND"
- "MPI:TRANSFER/SEND/COPY" + `DETAILED-STATES` >= 2: "MPI:TRANSFER:SEND:COPY"
- "/MPI:INTERNAL" + `DETAILED-STATES` 0: "" = not logged
- "/MPI:INTERNAL" + `DETAILED-STATES` 1: ":MPI:INTERNAL" = "MPI:INTERNAL"

If (and only if) the configuration option `DETAILED-STATES` causes the truncation of a certain state name, then entering that state is ignored if the process already is in that state.

Example of trace with `DETAILED-STATES` 0:

- enter "MPI:TRANSFER/WAIT" = enter "MPI:TRANSFER"
- enter "MPI:TRANSFER/COPY" = "MPI:TRANSFER" = ignored by ITC, return code != 0
- leave "MPI:TRANSFER/COPY" = ignored by application
- enter "MPI:TRANSFER/WAIT" = recursive call; ignored, too
- leave "MPI:TRANSFER/WAIT" = ignored by application
- leave "MPI:TRANSFER/WAIT" = leave "MPI:TRANSFER"

Same trace with `DETAILED-STATES` 1:

- enter "MPI:TRANSFER/WAIT" = enter "MPI:TRANSFER:WAIT"
- enter "MPI:TRANSFER/COPY" = enter "MPI:TRANSFER:COPY"
- leave "MPI:TRANSFER/COPY" = leave "MPI:TRANSFER:COPY"
- enter "MPI:TRANSFER/WAIT" = enter "MPI:TRANSFER:WAIT"
- leave "MPI:TRANSFER/WAIT" = leave "MPI:TRANSFER:WAIT"
- leave "MPI:TRANSFER/WAIT" = leave "MPI:TRANSFER:WAIT"

#### Fortran

```
VTENTERSTATE( name, statehandle, truncated, ierr )
```

#### Parameters:

**name** the name of the state, with colons and/or slashes as separators as described above

**Return values:**

**statehandle** must be initialized to zero before calling this function for the first time, then is set inside the function to the state handle which corresponds to the function which is logged

**truncated** set when calling the function for the first time: zero iff the full name is logged

**Returns:**

zero iff state was entered and [VT\\_leave\(\)](#) needs to be called

**int VT\_wakeup (void)**

Triggers the same additional actions as logging a function call, but without actually logging a call.

When ITC logs a function entry or exit it might also execute other actions, like sampling and logging counter data. If a function runs for a very long time, then ITC has no chance to execute these actions. To avoid that, the programmer can insert calls to this function into the source code of the long-running function.

**Fortran**

VTWAKEUP( ierr )

**Returns:**

error code

## 8.5 Defining and Recording Overlapping Scopes

**int VT\_scopedef (const char \* scopename, int classhandle, int scl1, int scl2, int \* scopehandle)**

In contrast to a state, which is entered and left with [VT\\_begin/VT\\_end\(\)](#) resp.

[VT\\_enter/VT\\_leave\(\)](#), a scope does not follow a stack based approach. It is possible to start a scope "a", then start scope "b" and stop "a" before "b":

```
|---- a ----|
|----- b ----|
```

A scope is identified by its name and class, just like functions. The source code locations that can be associated with it are just additional and optional attributes; they could be used to mark a static start and end of the scope in the source.

As functions, the *scopename* may consist of several components separated by a colon (:).

**Fortran**

VTSCOPEDEF( scopename, classhandle, scl1, scl2, scopehandle, ierr )

**Parameters:**

**scopename** the name of the scope

**classhandle** the class this scope belongs to (defined with [VT\\_classdef\(\)](#))

**scl1** any kind of SCL as defined with [VT\\_scldef\(\)](#), or [VT\\_NOSCL](#)

**scl2** any kind of SCL as defined with [VT\\_scldef\(\)](#), or [VT\\_NOSCL](#)

**Return values:**

**scopehandle** set to a numeric handle for the scope, needed by [VT\\_scopebegin\(\)](#)

**Returns:**

error code

***int VT\_scopebegin (int scopehandle, int scl, int \* seqnr)***

Starts a new instance of the scope previously defined with [VT\\_scopedef\(\)](#).

There can be more than one instance of a scope at the same time. In order to have the flexibility to stop an arbitrary instance, ITC assigns an intermediate identifier to it which can (but does not have to) be passed to [VT\\_scopeend\(\)](#). If the application does not need this flexibility, then it can simply pass 0 to [VT\\_scopeend\(\)](#).

**Fortran**

```
VTSCOPEBEGIN( scopehandle, scl, seqnr, ierr )
```

**Parameters:**

**scopehandle** the scope as defined by [VT\\_scopedef\(\)](#)

**scl** in contrast to the static SCL given in the scope definition this you can vary with each instance; pass [VT\\_NOSCL](#) if not needed

**Return values:**

**seqnr** is set to a number that together with the handle identifies the scope instance; pointer may be NULL

**Returns:**

error code

***int VT\_scopeend (int scopehandle, int seqnr, int scl)***

Stops a scope that was previously started with [VT\\_scopebegin\(\)](#).

**Fortran**

```
VTSCOPEEND( scopehandle, seqnr, scl )
```

**Parameters:**

**scopehandle** identifies the scope that is to be terminated

**seqnr** 0 terminates the most recent scope with the given handle, passing the seqnr returned from [VT\\_scopebegin\(\)](#) terminates exactly that instance

**scl** a dynamic SCL for leaving the scope

## 8.6 Defining Groups of Processes

ITC makes it possible to define an arbitrary, recursive group structure over the processes of an MPI application, and ITA is able to display profiling and communication statistics for these groups. Thus, a user can start with the top-level groups and walk down the hierarchy, “unfolding” interesting groups into ever more detail until he arrives at the level of processes or threads.

Groups are defined recursively with a simple bottom-up scheme: the [VT\\_groupdef\(\)](#) routine builds a new group from a list of already defined groups or processes, returning an integer group handle to identify the newly defined group. The following handles are predefined:

***enum VT\_Group*****Enumeration values:**

**VT\_ME** the calling thread/process.

**VT\_GROUP\_THREAD** Group of all threads.

**VT\_GROUP\_PROCESS** Group of all processes.

**VT\_GROUP\_CLUSTER** Group of all clusters.

To refer to non-local processes, the lookup routine `VT_getprocid()` translates between ranks in `MPI_COMM_WORLD` and handles that can be used for `VT_groupdef()`:

***int VT\_getprocid (int procindex, int \* procid)***

Get global id for process which is identified by process index.

If threads are supported, then this id refers to the group of all threads within the process, otherwise the result is identical to `VT_getthreadid( procindex, 0, procid )`.

**Fortran**

`VTGETPROCID( procindex, procid, ierr )`

**Parameters:**

***procindex*** index of process (0 <= procindex < N )

**Return values:**

***procidpointer*** to mem place where id is written to

**Returns:**

error code

The same works for threads:

***int VT\_getthreadid (int procindex, int thindex, int \* threadid)***

Get global id for the thread which is identified by the pair of process and thread index.

**Fortran**

`VTGETTHREADID( procindex, thindex, threadid, ierr )`

**Parameters:**

***procindex*** index of process (0 <= procindex < N )

***thindex*** index of thread

**Return values:**

***threadid*** pointer to mem place where id is written to

**Returns:**

error code

***int VT\_groupdef (const char \* name, int n\_members, int \* ids, int \* grouphandle)***

Defines a new group and returns a handle for it.

Groups are distinguished by their name and their members. The order of group members is preserved, which can lead to groups with the same name and same set of members, but different order of these members.

**Fortran**

`VTGROUPDEF( name, n_members, ids[], grouphandle, ierr )`

**Parameters:**

***name*** the name of the group

***n\_members*** number of entries in the *ids* array

***ids*** array where each entry is either:

- `VT_ME`
- `VT_GROUP_THREAD`



- [VT\\_GROUP\\_PROCESS](#)
- [VT\\_GROUP\\_CLUSTER](#)
- result of [VT\\_getthreadid\(\)](#), [VT\\_getprocid\(\)](#) or [VT\\_groupdef\(\)](#)

**Return values:**

**grouphandle** handle for the new group, or old handle if the group was defined already

**Returns:**

error code

To generate a new group that includes the processes with even ranks in MPI.COMM\_WORLD, you can code:

```
int *IDS = malloc(sizeof(*IDS)*(number_procs/2));
int i, even_group;
for( i = 0; i < number_procs; i += 2 )
    VT_getprocid(i, IDS + i/2);
VT_groupdef(``Even Group``, number_procs/2, IDS, &even_group);
```

If threads are used, then they automatically become part of a group that is formed by all threads inside the same process. The numbering of threads inside this group depends on the order in which threads call VT because they are registered the first time they invoke VT. The order can be controlled by calling [VT\\_registerthread\(\)](#) as the first API function with a positive parameter.

## 8.7 Defining and Recording Counters

ITC introduces the concept of counters to model numeric performance data that changes over the execution time. Counters can be used to capture the values of hardware performance counters, or of program variables (iteration counts, convergence rate, ...) or any other numerical quantity. An ITC counter is identified by its name, the counter class it belongs to (similar to the two-level symbol naming), and the type of its values (integer or floating-point) and the units that the values are quoted in (Example: MFlop/sec).

A counter can be attached to MPI processes to record process-local data, or to arbitrary groups. When using a group, then each member of the group will have its own instance of the counter and when a process logs a value it will only update the counter value of the instance the process belongs to.

Similar to other ITC objects, counters are referred to by integer counter handles that are managed automatically by the library.

To define a counter, the class it belongs to needs to be defined by calling [VT\\_classdef\(\)](#). Then, call [VT\\_countdef\(\)](#), and pass the following information:

- the counter name
- the data type

**enum VT\_CountData****Enumeration values:**

**VT\_COUNT\_INTEGER** Counter measures 64 bit integer value, passed to ITC API as a pair of high and low 32 bit integers.

**VT\_COUNT\_FLOAT** Counter measures 64 bit floating point value (native format).

**VT\_COUNT\_INTEGER64** Counter measures 64 bit integer value (native format).

**VT\_COUNT\_DATA** mask to extract the data format.

- the kind of data

**enum VT\_CountDisplay****Enumeration values:**

- VT\_COUNT\_ABSVAL** counter shall be displayed with absolute values.
- VT\_COUNT\_RATE** first derivative of counter values shall be displayed.
- VT\_COUNT\_DISPLAY** mask to extract the display type.

- the semantic associated with a sample value

**enum VT\_CountScope****Enumeration values:**

- VT\_COUNT\_VALID\_BEFORE** the value is valid until and at the current time.
- VT\_COUNT\_VALID\_POINT** the value is valid exactly at the current time, and no value is available before or or after it.
- VT\_COUNT\_VALID\_AFTER** the value is valid at and after the current time.
- VT\_COUNT\_VALID\_SAMPLE** the value is valid at the current time and samples a curve, so e.g. linear interpolation between sample values is possible
- VT\_COUNT\_SCOPE** mask to extract the scope.

- the counter's target, that is the process or group of processes it belongs to (**VT\_GROUP\_THREAD** for a thread-local counter, **VT\_GROUP\_PROCESS** for a process-local counter, or an arbitrary previously defined group handle)
- the lower and upper bounds
- the counter's unit (an arbitrary string like FLOP, Mbytes)

**int VT\_countdef** (*const char* \* name, *int* classhandle, *int* genre, *int* target, *const void* \* bounds, *const char* \* unit, *int* \* counterhandle)

Define a counter and get handle for it.

Counters are identified by their name (string) alone.

**Fortran**

VT\_COUNTDEF( name, classhandle, genre, target, bounds[], unit, counterhandle, ierr )

**Parameters:**

**name** string identifying the counter

**classhandle** class to group counters, handle must have been retrieved by **VT\_classdef**

**genre** bitwise or of one value from VT\_CountScope, VT\_CountDisplay and VT\_CountData

**target** target which the counter refers to (**VT\_ME**, **VT\_GROUP\_THREAD**, **VT\_GROUP\_PROCESS**, **VT\_GROUP\_CLUSTER** or thread/process-id or user-defined group handle ).



**bounds** array of lower and upper bounds (2x 64 bit float, 2x2 32 bit integer, 2x 64 bit integer  
-> 16 byte)

**unit** string identifying the unit for the counter (like Volt, pints etc.)


**Return values:**

**counterhandle** handle identifying the defined counter

**Returns:**

error code

The integer counters have 64-bit integer values, while the floating-point counters have a value domain of 64-bit IEEE floating point numbers. On systems that have no 64-bit int type in C, and for Fortran, the 64-bit values are specified using two 32-bit integers. Integers and floats are passed in the native byte order, but for [VT\\_COUNT\\_INTEGER](#) the integer with the higher 32 bits needs to be given first on all platforms:



At any time during execution, a process can record a new value for any of the defined counters by calling one of the ITC API routines described below. To minimize the overhead, it is possible to set the values of several counters with one call by passing an integer array of counter handles and a corresponding array of values. In C, it is possible to mix 64-bit integers and 64-bit floating point values in one value array; in Fortran, the language requires that the value array contains either all integer or all floating point values.

**int VT\_countval (int ncounters, int \* handles, void \* values)**

Record counter values.

Values are expected as two 4-byte integers, one 8-byte integer or one 8-byte double, according to the counter it refers to.

**Fortran**

VT\_COUNTVAL( ncounters, handles[], values[], ierr )

**Parameters:**

**ncounters** number of counters to be recorded

**handles** array of ncounters many handles (previously defined by [VT\\_countdef](#))

**values** array of ncounters many values, value[i] corresponds to handles[i].

**Returns:**

error code

The examples directory contains `counterscope.c`, which demonstrates all of these facilities.

## 8.8 Recording Communication Events

These are API calls that allow logging of message send and receive and MPI-style collective operations. Because they are modelled after MPI operations, they use the same kind of communicator to define the context for the operation:



**enum \_VT\_CommIDs**

Logging send/receive events evaluates process rank local within the active communicator, and matches events only if they are taking place in the same communicator (in other words, it is the same behaviour as in MPI).

Defining new communicators is currently not supported, but the predefined ones can be used.

**Enumeration values:**

**VT\_COMM\_INVALID** invalid ID, do not pass to ITC.

**VT\_COMM\_WORLD** global ranks are the same as local ones.

**VT\_COMM\_SELF** communicator that only contains the active process.

**int VT\_log\_sendmsg (int other\_rank, int count, int tag, int commid, int sclhandle)**

Logs sending of a message.

**Fortran**

```
VTLOGSENDMSG( other_rank, count, tag, commid, sclhandle, ierr )
```

**Parameters:**

**my\_rank** rank of the sending process

**other\_rank** rank of the target process

**count** number of bytes sent

**tag** tag of the message

**commid** numeric ID for the communicator ([VT\\_COMM\\_WORLD](#), [VT\\_COMM\\_SELF](#), or see [VT\\_commid\(\)](#))

**sclhandle** handle as defined by [VT\\_scldef](#), or [VT\\_NOSCL](#)

**Returns:**

error code

**int VT\_log\_recvmsg (int other\_rank, int count, int tag, int commid, int sclhandle)**

Logs receiving of a message.

**Fortran**

```
VTLOGRECVMSG( other_rank, count, tag, commid, sclhandle, ierr )
```

**Parameters:**

**my\_rank** rank of the receiving process

**other\_rank** rank of the source process

**count** number of bytes sent

**tag** tag of the message

**commid** numeric ID for the communicator ([VT\\_COMM\\_WORLD](#), [VT\\_COMM\\_SELF](#), or see [VT\\_commid\(\)](#))

**sclhandle** handle as defined by [VT\\_scldef](#), or [VT\\_NOSCL](#)

**Returns:**

error code

The next three calls require a little extra care, because they generate events that not only have a time stamp, but also a duration. This means that you need to take a time stamp first, then do the operation and finally log the event.



***int VT\_log\_msgevent*** (*int sender, int receiver, int count, int tag, int commid, double sendts, int sendscl, int recvscl*)

Logs sending and receiving of a message.

**Fortran**

VTLOGMSGEVENT( sender, receiver, count, tag, commid, sendts, sendscl, recvscl, ierr )

**Parameters:**

**sender** rank of the sending process

**receiver** rank of the target process

**count** number of bytes sent

**tag** tag of the message

**commid** numeric ID for the communicator ([VT\\_COMM\\_WORLD](#), [VT\\_COMM\\_SELF](#), or see [VT\\_commdf\(\)](#))

**sendts** time stamp obtained with [VT\\_timestamp\(\)](#)

**sendscl** handle as defined by [VT\\_scldef\(\)](#) for the source code location where the message was sent, or [VT\\_NOSCL](#)

**recvscl** the same for the receive location

**Returns:**

error code

***int VT\_log\_op*** (*int opid, int commid, int root, int bsend, int brecv, double startts, int sclhandle*)

Logs the duration and amount of transferred data of an operation for one process.

**Fortran**

VTLOGOP( opid, commid, root, bsend, brecv, startts, sclhandle, ierr )

**Parameters:**

**opid** id of the operation; must be one of the predefined constants in enum `_VT_OpTypes`

**commid** numeric ID for the communicator; see [VT\\_log\\_sendmsg\(\)](#) for valid numbers

**root** rank of the root process in the communicator (ignored for operations without root, must still be valid, though)

**bsend** bytes sent by process (ignored for operations that send no data)

**brecv** bytes received by process (ignored for operations that receive no data)

**startts** the start time of the operation (as returned by [VT\\_timestamp\(\)](#))

**sclhandle** handle as defined by [VT\\_scldef](#), or [VT\\_NOSCL](#)

**Returns:**

error code

***int VT\_log\_opevent*** (*int opid, int commid, int root, int numprocs, int \* bsend, int \* brecv, double \* startts, int sclhandle*)

Logs the duration and amount of transferred data of an operation for all involved processes at once.

ITC knows which processes send and receive data in each operation. Unused byte counts are ignored when writing the trace, so they can be left uninitialized, but NULL is not allowed as array address even if no entry is used at all.

**Fortran**

VTLOGOPEVENT( opid, commid, root, numprocs, bsend, brecv, startts, sclhandle, ierr )

**Parameters:****opid** id of the operation; must be one of the predefined constants in enum `_VT_OpTypes`**commid** numeric ID for the communicator; see [VT\\_log\\_sendmsg\(\)](#) for valid numbers**root** rank of the root process in the communicator (ignored for operations without root, must still be valid, though)**numprocs** the number of processes in the communicator**bsend** bytes sent by process**brecv** bytes received by process**startts** the start time of the operation (as returned by [VT\\_timestamp\(\)](#))**sclhandle** handle as defined by [VT\\_scldf](#), or [VT\\_NOSCL](#)**Returns:**

error code

**enum `_VT_OpTypes`**These are operation ids that can be passed to [VT\\_log\\_op\(\)](#).

Their representation in the trace file matches that of the equivalent MPI operation.

User-defined operations are currently not supported.

**Enumeration values:****VT\_OP\_INVALID** undefined operation, should not be passed to ITC.**VT\_OP\_BARRIER****VT\_OP\_BCAST****VT\_OP\_GATHER****VT\_OP\_GATHERV****VT\_OP\_SCATTER****VT\_OP\_SCATTERV****VT\_OP\_ALLGATHER****VT\_OP\_ALLGATHERV****VT\_OP\_ALLTOALL****VT\_OP\_ALLTOALLV****VT\_OP\_REDUCE****VT\_OP\_ALLREDUCE****VT\_OP\_REDUCE\_SCATTER****VT\_OP\_SCAN****VT\_OP\_COUNT** number of predefined operations.

Having a duration also introduces the problem of (possibly) having overlapping operations, which has to be taken care of with the following two calls:

**int [VT\\_begin\\_unordered](#) (void)**



Starts a period with out-of-order events.

Most API functions log events with just one time stamp which is taken when the event is logged. That guarantees strict chronological order of the events.

`VT_log_msgevent()` and `VT_log_opevent()` are logged when the event has finished with a start time taken earlier with `VT_timestamp()`. This can break the chronological order, e.g. like in the following two examples:

```
t1: VT_timestamp()      "start message"
t2: VT_end()           "leave function"
t3: VT_log_msgevent( t1 ) "finish message"
t1: VT_timestamp()      "start first message"
t2: VT_timestamp()      "start second message"
t3: VT_log_msgevent( t1 ) "finish first message"
t4: VT_log_msgevent( t2 ) "finish second message"
```

In other words, it is okay to just log a complex event if and only if no other event is logged between its start and end in this thread. "logged" in this context includes other complex events that are logged later, but with a start time between the other events start and end time.

In all other cases you have to alert ITC of the fact that out-of-order events will follow by calling `VT_begin_unordered()` before and `VT_end_unordered()` after these events. When writing the events into the trace file ITC increases a counter per thread when it sees a `VT_begin_unordered()` and decrease it at a `VT_end_unordered()`. Events are remembered and sorted until the counter reaches zero, or till the end of the data.

This means that:

- unordered periods can be nested,
- it is not necessary to close each unordered period at the end of the trace,
- but not closing them properly in the middle of a trace will force ITC to use a lot more memory when writing the trace (proportional to the number of events till the end of the trace).

#### Fortran

```
VTBEGINUNORDERED( ierr )
```

***int VT\_end\_unordered (void)***

Close a period with out-of-order events that was started with `VT_begin_unordered()`.

#### Fortran

```
VTENDUNORDERED( ierr )
```

## 8.9 Additional API Calls in libVTcs

***int VT\_abort (void)***

Abort a `VT_initialize()` or `VT_finalize()` call running concurrently in a different thread.

This call will not block, but it might still take a while before the aborted calls actually return. They will return either successfully (if they have completed without aborting) or with an error code.



**Returns:**

0 if abort request was sent successfully, else error code

***int VT\_clientinit (int procid, const char \* clientname, const char \*\* contact)***

Initializes communication in a client/server application.

Must be called before [VT\\_initialize\(\)](#) in the client of the application. There are three possibilities:

1. client is initialized first, which produces a contact string that must be passed to the server (\*contact == NULL)
2. the server was started first, its contact string is passed to the clients (\*contact == result of [VT\\_serverinit\(\)](#) with the prefix "S" - this prefix must be added by the application)
3. a process spawns children dynamically, its contact string is given to its children (\*contact == result of [VT\\_serverinit\(\)](#) or [VT\\_clientinit\(\)](#))

**Parameters:**

***procid*** All clients must be enumerated by the application. This will become the process id of the local client inside its [VT\\_COMM\\_WORLD](#). If the VTserver is used, then enumeration must start at 1 because VTserver always gets rank 0. Threads can be enumerated automatically by ITC or by the client by calling [VT\\_registerthread\(\)](#).

***clientname*** The name of the client. Currently only used for error messages. Copied by ITC.

**Return values:**

***contact*** Will be set to a string which tells other processes how to contact this process. Guaranteed not to contain spaces. The client may copy this string, but doesn't have to, because ITC will not free this string until [VT\\_finalize\(\)](#) is called.

**Returns:**

error code

***int VT\_serverinit (const char \* servername, int numcontacts, const char \* contacts[], const char \*\* contact)***

Initializes one process as the server that contacts the other processes and coordinates trace file writing.

The calling process always gets rank #0.

There are two possibilities:

1. collect all infos from the clients and pass them here (numcontacts >= 0, contacts != NULL)
2. start the server first, pass its contact string to the clients (numcontacts >= 0, contacts == NULL)

This call replaces starting the VTserver executable in a separate process. Parameters that used to be passed to the VTserver to control tracing and trace writing can be passed to [VT\\_initialize\(\)](#) instead.

**Parameters:**

***servername*** similar to clientname in [VT\\_clientinit\(\)](#): the name of the server. Currently only used for error messages. Copied by ITC.

***numcontacts*** number of client processes



**contacts** contact string for each client process (order is irrelevant); copied by ITC

**Return values:**

**contact** Will be set to a string which tells spawned children how to contact this server. Guaranteed not to contain spaces. The server may copy this string, but doesn't have to, because ITC will not free this string until [VT\\_finalize\(\)](#) is called. \*contact must have been set to NULL before calling this function.

**Returns:**

error code

***int VT\_attach (int root, int comm, int numchildren, int \* childcomm)***

Connect to several new processes.

These processes must have been spawned already and need to know the contact string of the root process when calling [VT\\_clientinit\(\)](#).

comm == [VT\\_COMM\\_WORLD](#) is currently not implemented. It has some design problems: if several children want to use [VT\\_COMM\\_WORLD](#) to recursively spawn more processes, then their parents must also call [VT\\_attach\(\)](#), because they are part of this communicator. If the VTserver is part of the initial [VT\\_COMM\\_WORLD](#), then [VT\\_attach\(\)](#) with [VT\\_COMM\\_WORLD](#) won't work, because the VTserver does not know about the spawned processes and never calls [VT\\_attach\(\)](#).

**Parameters:**

**root** rank of the process that the spawned processes will contact

**comm** either [VT\\_COMM\\_SELF](#) or [VT\\_COMM\\_WORLD](#): in the first case root must be 0 and the spawned processes are connected to just the calling process. In the latter case all processes that share this [VT\\_COMM\\_WORLD](#) must call [VT\\_attach\(\)](#) and are included in the new communicator. root then indicates whose contact infos were given to the children.

**numchildren** number of children that the spawning processes will wait for

**Return values:**

**childcomm** an identifier for a new communicator that includes the parent processes in the same order as in their [VT\\_COMM\\_WORLD](#), followed by the child processes in the order specified by their procid argument in [VT\\_clientinit\(\)](#). The spawned processes will have access to this communicator via [VT\\_get\\_parent\(\)](#).

**Returns:**

error code

***int VT\_get\_parent (int \* parentcomm)***

Returns the communicator that connects the process with its parent, or [VT\\_COMM\\_INVALID](#) if not spawned.

**Return values:**

**parentcomm** set to the communicator number that can be used to log communication with parents

**Returns:**

error code

## 8.10 C++ API

These are wrappers around the C API calls which simplify instrumentation of C++ source code and ensure correct tracing if exceptions are used. Because all the member functions are provided as inline functions it is sufficient to include VT.h to use these classes with every C++ compiler.

Here are some examples how the C++ API can be used. `nohandles()` uses the simpler interface without storing handles, while `handles()` saves these handles in static instances of the definition classes for later reuse when the function is called again:

```
void nohandles()
{
    VT_Function func( "nohandles", "C++ API", __FILE__, __LINE__ );
}
void handles()
{
    static VT_SclDef scldef( __FILE__, __LINE__ );
    // VT_SCL_DEF_CXX( scldef ) could be used instead
    static VT_FuncDef funcdef( "handles", "C++ API" );
    VT_Function func( funcdef, scldef );
}
int main( int argc, char **argv )
{
    VT_Region region( "call nohandles()", "main" );
    nohandles();
    region.end();
    handles();
    handles();
    return 0;
}
```

### 8.10.1 VT\_FuncDef Class Reference

Defines a function on request and then remembers the handle.

#### Public Methods

- [VT\\_FuncDef](#) (const char \*symname, const char \*classname)
- int [GetHandle](#) ()

#### 8.10.1.1 Detailed Description

Defines a function on request and then remembers the handle.

Can be used to avoid the overhead of defining the function several times in [VT\\_Function](#).



### 8.10.1.2 Constructor & Destructor Documentation

### 8.10.1.3 VT\_FuncDef::VT\_FuncDef (const char \* *symname*, const char \* *classname*)

### 8.10.1.4 Member Function Documentation

### 8.10.1.5 int VT\_FuncDef::GetHandle ()

Checks whether the function is defined already or not.

Returns handle as soon as it is available, else 0. Defining the function may be impossible e.g. because ITC was not initialized or ran out of memory.

## 8.10.2 VT\_SclDef Class Reference

Defines a source code location on request and then remembers the handle.

### Public Methods

- [VT\\_SclDef](#) (const char \**file*, int *line*)
- int [GetHandle](#) ()

### 8.10.2.1 Detailed Description

Defines a source code location on request and then remembers the handle.

Can be used to avoid the overhead of defining the location several times in [VT\\_Function](#). Best used together with the define [VT\\_SCL\\_DEF\\_CXX\(\)](#).

### 8.10.2.2 Constructor & Destructor Documentation

### 8.10.2.3 VT\_SclDef::VT\_SclDef (const char \* *file*, int *line*)

### 8.10.2.4 Member Function Documentation

### 8.10.2.5 int VT\_SclDef::GetHandle ()

Checks whether the scl is defined already or not.

Returns handle as soon as it is available, else 0. Defining the function may be impossible e.g. because ITC was not initialized or ran out of memory.

**#define** [VT\\_SCL\\_DEF\\_CXX](#)(*\_sclvar*)

This preprocessor macro creates a static source code location definition for the current file and line in C++.

**Parameters:**

*\_sclvar* name of the static variable which is created



### 8.10.3 VT\_Function Class Reference

In C++ an instance of this class should be created at the beginning of a function.

#### Public Methods

- [VT\\_Function](#) (const char \*symname, const char \*classname)
- [VT\\_Function](#) (const char \*symname, const char \*classname, const char \*file, int line)
- [VT\\_Function](#) (VT\_FuncDef &funcdef)
- [VT\\_Function](#) (VT\_FuncDef &funcdef, VT\_SclDef &scldef)
- [~VT\\_Function](#) ()

#### 8.10.3.1 Detailed Description

In C++ an instance of this class should be created at the beginning of a function.

The constructor will then log the function entry, and the destructor the function exit.

Providing a source code location for the function exit manually is not supported, because this source code location would have to define where the function returns to. This cannot be determined at compile time.

#### 8.10.3.2 Constructor & Destructor Documentation

##### 8.10.3.3 VT\_Function::VT\_Function (const char \* *symname*, const char \* *classname*)

Defines the function with [VT\\_classdef\(\)](#) and [VT\\_funcdef\(\)](#), then enters it.

This is less efficient than defining the function once and then reusing the handle. Silently ignores errors, like e.g. uninitialized ITC.

**Parameters:**

- symname*** the name of the function
- classname*** the class this function belongs to

##### 8.10.3.4 VT\_Function::VT\_Function (const char \* *symname*, const char \* *classname*, const char \* *file*, int *line*)

Same as previous constructor, but also stores information about where the function is located in the source code.

**Parameters:**

- symname*** the name of the function
- classname*** the class this function belongs to
- file*** name of source file, may but does not have to include path
- line*** line in this file where function starts

##### 8.10.3.5 VT\_Function::VT\_Function (VT\_FuncDef & *funcdef*)

This is a more efficient version which supports defining the function only once.

**Parameters:**

- funcdef*** this is a reference to the (usually static) instance that defines and remembers the function handle



### 8.10.3.6 VT\_Function::VT\_Function (VT\_FuncDef & funcdef, VT\_SclDef & scldef)

This is a more efficient version which supports defining the function and source code location only once.

**Parameters:**

**funcdef** this is a reference to the (usually static) instance that defines and remembers the function handle

**scldef** this is a reference to the (usually static) instance that defines and remembers the scl handle

### 8.10.3.7 VT\_Function::~~VT\_Function ()

the destructor marks the function exit.

## 8.10.4 VT\_Region Class Reference

This is similar to [VT\\_Function](#), but should be used to mark regions within a function.

### Public Methods

- void [begin](#) (const char \*symname, const char \*classname)
- void [begin](#) (const char \*symname, const char \*classname, const char \*file, int line)
- void [begin](#) ([VT\\_FuncDef](#) &funcdef)
- void [begin](#) ([VT\\_FuncDef](#) &funcdef, [VT\\_SclDef](#) &scldef)
- void [end](#) ()
- void [end](#) (const char \*file, int line)
- void [end](#) ([VT\\_SclDef](#) &scldef)
- [VT\\_Region](#) ()
- [VT\\_Region](#) (const char \*symname, const char \*classname)
- [VT\\_Region](#) (const char \*symname, const char \*classname, const char \*file, int line)
- [VT\\_Region](#) ([VT\\_FuncDef](#) &funcdef)
- [VT\\_Region](#) ([VT\\_FuncDef](#) &funcdef, [VT\\_SclDef](#) &scldef)
- [~VT\\_Region](#) ()

#### 8.10.4.1 Detailed Description

This is similar to [VT\\_Function](#), but should be used to mark regions within a function.

The difference is that source code locations can be provided for the beginning and end of the region, and one instance of this class can be used to mark several regions in one function.

#### 8.10.4.2 Constructor & Destructor Documentation

#### 8.10.4.3 VT\_Region::VT\_Region ()

The default constructor does not start the region yet.



#### 8.10.4.4 VT\_Region::VT\_Region (const char \* *symname*, const char \* *classname*)

Enter region when it is created.

#### 8.10.4.5 VT\_Region::VT\_Region (const char \* *symname*, const char \* *classname*, const char \* *file*, int *line*)

Same as previous constructor, but also stores information about where the region is located in the source code.

#### 8.10.4.6 VT\_Region::VT\_Region (VT\_FuncDef & *funcdef*)

This is a more efficient version which supports defining the region only once.

#### 8.10.4.7 VT\_Region::VT\_Region (VT\_FuncDef & *funcdef*, VT\_SciDef & *scidef*)

This is a more efficient version which supports defining the region and source code location only once.

#### 8.10.4.8 VT\_Region::~~VT\_Region ()

the destructor marks the region exit.

#### 8.10.4.9 Member Function Documentation

#### 8.10.4.10 void VT\_Region::begin (const char \* *symname*, const char \* *classname*)

Defines the region with [VT\\_classdef\(\)](#) and [VT\\_funcdef\(\)](#), then enters it.

This is less efficient than defining the region once and then reusing the handle. Silently ignores errors, like e.g. uninitialized ITC.

**Parameters:**

***symname*** the name of the region

***classname*** the class this region belongs to

#### 8.10.4.11 void VT\_Region::begin (const char \* *symname*, const char \* *classname*, const char \* *file*, int *line*)

Same as previous [begin\(\)](#), but also stores information about where the region is located in the source code.

**Parameters:**

***symname*** the name of the region

***classname*** the class this region belongs to

***file*** name of source file, may but does not have to include path

***line*** line in this file where region starts



#### 8.10.4.12 void VT\_Region::begin (VT\_FuncDef & funcdef)

This is a more efficient version which supports defining the region only once.

**Parameters:**

**funcdef** this is a reference to the (usually static) instance that defines and remembers the region handle

#### 8.10.4.13 void VT\_Region::begin (VT\_FuncDef & funcdef, VT\_SciDef & scldef)

This is a more efficient version which supports defining the region and source code location only once.

**Parameters:**

**funcdef** this is a reference to the (usually static) instance that defines and remembers the region handle

**scldef** this is a reference to the (usually static) instance that defines and remembers the scl handle

#### 8.10.4.14 void VT\_Region::end ()

Leaves the region.

#### 8.10.4.15 void VT\_Region::end (const char \* file, int line)

Same as previous `end()`, but also stores information about where the region ends in the source code.

**Parameters:**

**file** name of source file, may but does not have to include path

**line** line in this file where region starts

#### 8.10.4.16 void VT\_Region::end (VT\_SciDef & scldef)

This is a more efficient version which supports defining the source code location only once.

**Parameters:**

**scldef** this is a reference to the (usually static) instance that defines and remembers the scl handle

## Chapter 9

# ITC Configuration

### 9.1 Configuring Intel(R) Trace Collector

With a configuration file, the user can customize various aspects of ITC's operation and define trace data filters.

### 9.2 Specifying Configuration Options

The environment variable `VT_CONFIG` can be set to the name of an ITC configuration file. If this file exists, it is read and parsed by the process specified with `VT_CONFIG_RANK` (or 0 as default). The values of `VT_CONFIG` have to be consistent over all processes, although it need not be set for all of them. A relative path is interpreted as starting from the current working directory; an absolute path is safer, because `mpirun` may start your processes in a different directory than you'd expect!

In addition to specifying options in a config file, all options have an equivalent environment variable. These variables are checked by the process that reads the config file after it has parsed the file, so the variables override the config file options. Some options like "SYMBOL" may appear several times in the config file. A variable may contain line breaks to achieve the same effect.

The environment variable names are listed below in square brackets [] in front of the config option. Their names are always the same as the options, but with the prefix "VT\_" and hyphens replaced with underscores.

Finally, it is also possible to specify configuration options on the command line of a program. The only exception are Fortran programs (because ITC's access to command line parameters is limited there). To avoid conflicts between ITC's parameters and normal application parameters, only parameters following the special `-itc-args` are interpreted by ITC. To continue with the application's normal parameters, `-itc-args-end` may be used. There may be more than one block of ITC arguments on the command line.

### 9.3 Configuration Format

The configuration file is a plain ASCII file containing a number of directives, one per line; any line starting with the # character is ignored. Within a line, whitespace separates fields, and double

quotation marks have to be used to quote fields containing whitespace. Each directive consists of an identifier followed by arguments. With the exception of filenames, all text is case-insensitive. In the following discussion, items within angle brackets (< and >) denote arbitrary case-insensitive field values, and alternatives are put within square brackets ([ and ]) and separated by a vertical bar |.

Default values are given in round brackets after the argument template, unless the default is too complex to be given in a few words. In this case the text explains the default value. In general the default values are chosen so that features that increase the amount of trace data have to be enabled explicitly. Memory handling options default to keeping all trace records in memory until the application is finalized.

## 9.4 Syntax of Parameters

### 9.4.1 Time Value

Time values are usually specified as a pair of one floating point value and one character that represents the unit: c for microseconds, l for milliseconds, s for seconds, m for minutes, h for hours, d for days and w for weeks. These elementary times are added with a + sign. For instance, the string 1m+30s refers to one minute and 30 seconds of execution time.

### 9.4.2 Boolean Value

Boolean values are set to "on/true" to turn something on and "off/false" to turn it off. Just using the name of the option without the "on/off" argument is the same as "on".

### 9.4.3 Number of Bytes

The amount of bytes can be specified with optional suffices B/KB/MB/GB, which multiply the amount in front of them with  $1/1024/1024^2/1024^3$ . If no suffix is given the number specifies bytes.

## 9.5 Supported Directives

### LOGFILE-NAME

**Syntax:** <file name>

**Variable:** VT\_LOGFILE\_NAME

Specifies the name for the tracefile containing all the trace data. Can be an absolute or relative pathname; in the latter case, it is interpreted relative to the log prefix (if set) or the current working directory of the process writing it.

If unspecified, then the name is the name of the program plus ".avt" for ASCII, ".stf" for STF and ".single.stf" for single STF tracefiles. If one of these suffices is used, then they also determine the logfile format, unless the format is specified explicitly.

In the stftool the name has to be specified explicitly, either by using this option or as argument of the `-convert` or `-move` switch.

**PROGNAME****Syntax:** <file name>**Variable:** [VT\\_PROGNAME](#)

This option can be used to provide a fallback for the executable name in case of ITC not being able to determine this name from the program arguments. It is also the base name for the trace file.

In Fortran it may be technically impossible to determine the name of the executable automatically and ITC may need to read the executable to find source code information (see [PCTRACE](#) config option). "UNKNOWN" is used if the file name is unknown and not specified explicitly.

**LOGFILE-FORMAT****Syntax:** [ASCII|STF|STFSINGLE|SINGLESTF]**Variable:** [VT\\_LOGFILE\\_FORMAT](#)**Default:** STF

Specifies the format of the tracefile. ASCII is the traditional Vampir file format where all trace data is written into one file. It is human-readable.

The Structured Trace File (STF) is a binary format which supports storage of trace data in several files and allows ITA to analyze the data without loading all of it, so it is more scalable. Writing it is only supported by ITC at the moment.

One trace in STF format consists of several different files which are referenced by one index file (.stf). The advantage is that different processes can write their data in parallel (see [STF-PROCS-PER-FILE](#), [STF-USE-HW-STRUCTURE](#)). SINGLESTF rolls all of these files into one (.single.stf), which can be read without unpacking them again. However, this format does not support distributed writing, so for large program runs with many processes the generic STF format is better.

**EXTENDED-VTF****Syntax:****Variable:** [VT\\_EXTENDED\\_VTF](#)**Default:** off in ITC, on in stftool

Several events can only be stored in STF, but not in VTF. ITC libraries default to writing valid VTF trace files and thus skip these events. This option enables writing of non-standard VTF records in ASCII mode that ITA would complain about. In the stftool the default is to write these extended records, because the output is more likely to be parsed by scripts rather than ITA.

**PROTOFILE-NAME****Syntax:** <file name>**Variable:** [VT\\_PROTOFILE\\_NAME](#)

Specifies the name for the protocol file containing the config options and (optionally) summary statistics for a program run. Can be an absolute or relative pathname; in the latter case, it is interpreted relative to the current working directory of the process writing it.

If unspecified, then the name is the name of the tracefile with the suffix ".prot".

**LOGFILE-PREFIX****Syntax:** <directory name>**Variable:** [VT\\_LOGFILE\\_PREFIX](#)

Specifies the directory of the trace or log file. Can be an absolute or relative pathname; in the latter case, it is interpreted relative to the current working directory of the process writing it.

**CURRENT-DIR****Syntax:** <directory name>**Variable:** [VT\\_CURRENT\\_DIR](#)

ITC will use the current working directory of the process that reads the configuration on all processes to resolve relative path names. You can override the current working directory with this option.

**VERBOSE**

**Syntax:** [on|off|<level>]

**Variable:** VT\_VERBOSE

**Default:** on

Enables or disables additional output on stderr. <level> is a positive number, with larger numbers enabling more output:

- 0 (= off) disables all output
- 1 (= on) enables only one final message about generating the result
- 2 enables general progress reports by the main process
- 3 enables detailed progress reports by the main process
- 4 the same, but for all processes (if multiple processes are used at all)

Levels larger than 2 may contain output that only makes sense to the developers of ITC.

**LOGFILE-RANK**

**Syntax:** <rank>

**Variable:** VT\_LOGFILE\_RANK

**Default:** 0

Determines which process creates and writes the tracefile in MPI\_Finalize(). Default value is the process reading the configuration file, or the process with rank 0 in MPI\_COMM\_WORLD.

**STOPFILE-NAME**

**Syntax:** <file name>

**Variable:** VT\_STOPFILE\_NAME

Specifies the name of a file which indicates that ITC should stop the application prematurely and write a tracefile. This works only with the fail-safe ITC libraries. On Linux\* systems the same behaviour can be achieved by sending the signal SIGINT to one of the application processes, but this is not possible on Microsoft\* Windows\*.

If specified, ITC checks for the existence of such a file from time to time. If detected, the stop file is removed again and the shutdown is initiated.

**PLUGIN**

**Syntax:** <plugin name>

**Variable:** VT\_PLUGIN

If this option is used, then ITC activates the given plugin after initialization. The plugin takes over responsibility for all function wrappers and normal tracing will be disabled. Most of the normal configuration options will have no effect. Refer to the documentation of the plugin that you want to use for further information.

**CHECK**

**Syntax:** <pattern> <on|off>

**Variable:** VT\_CHECK

**Default:** on

Enables or disables error checks matching the pattern.

**CHECK-MAX-ERRORS**

**Syntax:** <number>

**Variable:** VT\_CHECK\_MAX\_ERRORS

**Default:** 1





## 9.5. SUPPORTED DIRECTIVES

---

Number of errors that has to be reached by a process before aborting the application. 0 disables the limit. Some errors are fatal and always cause an abort. Errors are counted per-process to avoid the need for communication among processes, as that has several drawbacks which outweigh the advantage of a global counter.

Errors usually should not be ignored because they change the behavior of the application, thus the default value stops immediately when the first such error is found.

### CHECK-MAX-REPORTS

**Syntax:** <number>

**Variable:** `VT_CHECK_MAX_REPORTS`

**Default:** 0

Number of reports (regardless whether they contain warnings or errors) that has to be reached by a process before aborting the application. 0 disables the limit. Just as with `CHECK-MAX-ERRORS` this is a per-process counter.

It is disabled by default because the `CHECK-SUPPRESSION-LIMIT` setting already ensures that each type of error or warning is only reported a limited number of times. Setting `CHECK-MAX-REPORTS` would help to also automatically shut down the application, if that is desired.

### CHECK-SUPPRESSION-LIMIT

**Syntax:** <number>

**Variable:** `VT_CHECK_SUPPRESSION_LIMIT`

**Default:** 10

Maximum number of times a specific error or warning is reported before suppressing further reports about it. The application continues to run and other problems will still be reported. Just as with `CHECK-MAX-ERRORS` these are a per-process counters.

Note that this only counts per error check and does not distinguish between different incarnations of the error in different parts of the application.

### CHECK-TIMEOUT

**Syntax:** <time>

**Variable:** `VT_CHECK_TIMEOUT`

**Default:** 5s

After stopping one process because it cannot or is not allowed to continue, the other processes are allowed to continue for this amount of time to see whether they run into other errors.

### CHECK-MAX-PENDING

**Syntax:** <number>

**Variable:** `VT_CHECK_MAX_PENDING`

**Default:** 20

Upper limit of pending messages that are reported per `GLOBAL:MSG:PENDING` error.

### CHECK-MAX-REQUESTS

**Syntax:** <number>

**Variable:** `VT_CHECK_MAX_REQUESTS`

**Default:** 100

Each time the total number of active requests or inactive persistent requests exceeds a multiple of this threshold a `LOCAL:REQUEST:NOT_FREED` warning is printed with a summary of the calls where those requests were created.

Set this to 0 to disable just the warning at runtime without also disabling the warnings at the end of the application run. Disable the `LOCAL:REQUEST:NOT_FREED` check to suppress all warnings.

### CHECK-MAX-DATATYPES

**Syntax:** <number>

**Variable:** `VT_CHECK_MAX_DATATYPES`

**Default:** 1000

Each time the total number of currently defined datatypes exceeds a multiple of this threshold a `LOCAL:DATATYPE:NOT_FREED` warning is printed with a summary of the calls where those requests were created.

Set this to 0 to disable the warning.

### CHECK-LEAK-REPORT-SIZE

**Syntax:** <number>

**Variable:** `VT_CHECK_LEAK_REPORT_SIZE`

**Default:** 10

Determines the number of call locations to include in a summary of leaked requests or datatypes. By default only the "top ten" of the calls which have no matching free call are printed.

### DETAILED-STATES

**Syntax:** [on|off|<level>]

**Variable:** `VT_DETAILED_STATES`

**Default:** off

Enables or disables logging of more information in calls to `VT_enterstate()`. That function might be used by certain MPI implementations, runtime systems or applications to log internal states. If that is the case, it will be mentioned in the documentation of those components.

<level> is a positive number, with larger numbers enabling more details:

- 0 (= off) suppresses all additional states
- 1 (= on) enables one level of additional states
- 2, 3, ... enables even more details

### ENTER-USERCODE

**Syntax:** [on|off]

**Variable:** `VT_ENTER_USERCODE`

**Default:** on in most cases, off for Java function tracing

Usually ITC enters the `Application:User_Code` state automatically when registering a new thread. This make little sense when function profiling is enabled, because then the user can choose whether he wants the `main()` function or the entry function of a child thread to be logged or not. Therefore it is always turned off for Java function tracing. In all other cases it can be turned off manually with this configuration option.

However, without automatically entering this state and without instrumenting functions threads might be outside of any state and thus not visible in the trace although they exist. This may or may not be intended.

### COUNTER

**Syntax:** <pattern> [on|off]

**Variable:** `VT_COUNTER`

Enables or disables a counter whose name matches the pattern. By default all counters defined manually are enabled, whereas counters defined and sampled automatically by ITC are disabled. Those automatic counters are not supported for every platform.

### INTERNAL-MPI

**Syntax:** [on|off]

**Variable:** `VT_INTERNAL_MPI`



**Default:** on

Allows tracing of events inside the MPI implementation. This is enabled by default, but even then it still requires an MPI implementation which actually records events. The ITC documentation describes in more detail how an MPI implementation might do that.

### PCTRACE

**Syntax:** [on|off|<trace levels>|<skip levels>:<trace levels>]

**Variable:** VT\_PCTRACE

**Default:** off for performance analysis, enabled otherwise

Some platforms support the automatic stack sampling for MPI calls and user-defined events. ITC then remembers the Program Counter (PC) values on the call stack and translates them to source code locations based on debug information in the executable. It can sample a certain number of levels (<trace levels>) and skip the initial levels (<skip levels>). Both values can be in the range of 0 to 15.

Skipping levels is useful when a function is called from within another library and the source code locations within this library shall be ignored. ON is equivalent to 0:1 (no skip levels, one trace level).

The value specified with PCTRACE applies to all symbols that are not matched by any filter rule or where the relevant filter rule sets the logging state to ON. In other words, an explicit logging state in a filter rule overrides the value given with PCTRACE.

### PCTRACE-FAST

**Syntax:** [on|off]

**Variable:** VT\_PCTRACE\_FAST

**Default:** on for performance tracing, off for correctness checking

Controls whether the fast, but less reliable stack unwinding is used or the slower, but less error-prone unwinding via libunwind. On Itanium libunwind is always used. The fast unwinding relies on frame pointers, therefore all code must be compiled accordingly for it to work correctly.

### PCTRACE-CACHE

**Syntax:** [on|off]

**Variable:** VT\_PCTRACE\_CACHE

**Default:** on

When the reliable stack unwinding via libunwind is used, caching the previous stack back trace can reduce the number of times libunwind has to be called later on. When unwinding only a few levels this caching can negatively affect performance, therefore it can be turned off with this option.

### PROCESS

**Syntax:** <triplets> [on|off|no|discard]

**Variable:** VT\_PROCESS

**Default:** 0:N on

Specifies for which processes tracing is to be enabled. This option accepts a comma separated list of triplets, each of the form <start>:<stop>:<incr> specifying the minimum and maximum rank and the increment to determine a set of processes (similar to the Fortran 90 notation). Ranks are interpreted relative to MPI\_COMM\_WORLD, which means that they start with 0. The letter N can be used as maximum rank and is replaced by the current number of processes. F.i. to enable tracing only on odd process ranks, specify "PROCESS 0:N OFF" and "PROCESS 1:N:2 ON".

A process that is turned off can later turn logging on by calling VT\_traceon() (and vice versa). Using "no" disables ITC for a process completely to reduce the overhead even further, but also so that even VT\_traceon() cannot enable tracing.



"discard" is the same as "no", so data is collected and trace statistics will be calculated, but the collected data is not actually written into the trace file. This mode is useful if looking at the statistics is sufficient: in this case there is no need to write the trace data.

#### CLUSTER

**Syntax:** <triplets> [on|off|no|discard]

**Variable:** [VT\\_CLUSTER](#)

Same as [PROCESS](#), but filters based on the host number of each process. Hosts are distinguished by their name as returned by `MPI_Get_processor_name()` and enumerated according to the lowest rank of the MPI processes running on them.

#### MEM-BLOCKSIZE

**Syntax:** <number of bytes>

**Variable:** [VT\\_MEM\\_BLOCKSIZE](#)

**Default:** 64KB

ITC keeps trace data in chunks of main memory that have this size.

#### MEM-MAXBLOCKS

**Syntax:** <maximum number of blocks>

**Variable:** [VT\\_MEM\\_MAXBLOCKS](#)

**Default:** 4096

ITC will never allocate more than this number of blocks in main memory. If the maximum number of blocks is filled or allocating new blocks fails, then ITC will either flush some of them onto disk ([AUTOFLUSH](#)), overwrite the oldest blocks ([MEM-OVERWRITE](#)) or stop recording further trace data.

#### MEM-MINBLOCKS

**Syntax:** <minimum number of blocks after flush>

**Variable:** [VT\\_MEM\\_MINBLOCKS](#)

**Default:** 0

When ITC starts to flush some blocks automatically, then it can flush all (the default) or keep some in memory. The latter may be useful to avoid long delays or to avoid unnecessary disk activity.

#### MEM-INFO

**Syntax:** <threshold in bytes>

**Variable:** [VT\\_MEM\\_INFO](#)

**Default:** 500MB

If larger than zero, then ITC will print a message to `stderr` each time more than this amount of new data has been recorded. These messages tell how much data was stored in RAM and in the flush file, and can serve as a warning when too much data is recorded.

#### AUTOFLUSH

**Syntax:** [on|off]

**Variable:** [VT\\_AUTOFLUSH](#)

**Default:** on

If enabled (which it is by default), then ITC will append blocks that are currently in main memory to one flush file per process. During trace file generation this data is taken from the flush file, so no data is lost. The number of blocks remaining in memory can be controlled with [MEM-MINBLOCKS](#).

#### MEM-FLUSHBLOCKS

**Syntax:** <number of blocks>

**Variable:** [VT\\_MEM\\_FLUSHBLOCKS](#)

**Default:** 1024



## 9.5. SUPPORTED DIRECTIVES

---

This option controls when a background thread flushes trace data into the flush file without blocking the application. It has no effect if **AUTOFLUSH** is disabled. Setting this option to a negative value also disables the background flushing.

Flushing is started whenever the number of blocks in memory exceeds this threshold or when a thread needs a new block, but cannot get it without flushing.

If the number of blocks also exceeds **MEM-MAXBLOCKS**, then the application is stopped until the background thread has flushed enough data.

### **MEM-OVERWRITE**

**Syntax:** [on|off]

**Variable:** **VT\_MEM\_OVERWRITE**

**Default:** off

If auto flushing is disabled, then enabling this lets ITC overwrite the oldest blocks of trace data with more recent data.

### **FLUSH-PREFIX**

**Syntax:** <directory name>

**Variable:** **VT\_FLUSH\_PREFIX**

**Default:** content of env variables or `"/tmp"`

Specifies the directory of the flush file. Can be an absolute or relative pathname; in the latter case, it is interpreted relative to the current working directory of the process writing it.

On Unix systems, the flush file of each process will be created and immediately removed while the processes keep their file open. This has two effects:

- flush files do not clutter the file system if processes get killed prematurely
- during flushing, the remaining space on the file systems gets less although the file which grows is not visible any more

The file name is `"VT-flush-<program name>_<rank>-<pid>.dat"`, with `<rank>` being the rank of the process in `MPI_COMM_WORLD` and `<pid>` the Unix process id.

A good default directory is searched for among the candidates listed below in this order:

- first directory with more than 512MB
- failing that, directory with most available space

Candidates (in this order) are the directories referred to with these environment variables and hard-coded directory names:

- `BIGTEMP`
- `FASTTEMP`
- `TMPDIR`
- `TMP`
- `TMPVAR`
- `"/work"`
- `"/scratch"`
- `"/tmp"`

### **FLUSH-PID**

**Syntax:** [on|off]

**Variable:** **VT\_FLUSH\_PID**

**Default:** on

The `"-<pid>"` part in the flush file name is optional and can be disabled with `"FLUSH-PID off"`.

**ENVIRONMENT****Syntax:** [on|off]**Variable:** [VT\\_ENVIRONMENT](#)**Default:** on

Enables or disables logging of attributes of the runtime environment.

**STATISTICS****Syntax:** [on|off|<hash\_size>]**Variable:** [VT\\_STATISTICS](#)**Default:** off

Enables or disables statistics about messages and symbols. These statistics are gathered by ITC independently from logging them and stored in the tracefile. Apart from on and off it allows specifying the hash size used on each collecting thread. For extensively instrumented codes or for codes with a volatile communication pattern this might be useful to control its performance.

**STF-USE-HW-STRUCTURE****Syntax:** [on|off]**Variable:** [VT\\_STF\\_USE\\_HW\\_STRUCTURE](#)**Default:** usually on

If the STF format is used, then trace information can be stored in different files. If this option is enabled, then trace data of processes running on the same node are combined in one file for that node. This is enabled by default on most machines because it both reduces inter-node communication during trace file generation and resembles the access pattern during analysis. It is not enabled if each process is running on its own node.

This option can be combined with [STF-PROCS-PER-FILE](#) to reduce the number of processes whose data is written into the same file even further.

**STF-PROCS-PER-FILE****Syntax:** <number of processes>**Variable:** [VT\\_STF\\_PROCS\\_PER\\_FILE](#)**Default:** 16

In addition to or instead of combining trace data per node, the number of processes per file can be limited. This helps to restrict the amount of data that has to be loaded when analysing a sub-set of the processes.

If [STF-USE-HW-STRUCTURE](#) is enabled, then [STF-PROCS-PER-FILE](#) has no effect unless it is set to a value smaller than the number of processes running on a node. To get files that each contain exactly the data of <n> processes, set [STF-USE-HW-STRUCTURE](#) to OFF and [STF-PROCS-PER-FILE](#) to <n>.

In a single-process, multithreaded application trace this configuration option is used to determine the number of threads per file.

**STF-CHUNKSIZE****Syntax:** <number of bytes>**Variable:** [VT\\_STF\\_CHUNKSIZE](#)**Default:** 64KB

ITC uses so called anchors to navigate in STF files. This value determines how many bytes of trace data are written into a file before setting the next anchor. Using a low number allows more accurate access during analysis, but increases the overhead for storing and handling anchors.

**GROUP****Syntax:** <name> <name>|<triplet>[, ...]**Variable:** VT\_GROUP

This option defines a new group. The members of the group can be other groups or processes enumerated with triplets. Groups are identified by their name. It is possible to refer to automatically generated groups (Example: those for the nodes in the machine), however, groups generated with API functions have to be defined on the process which reads the config to be usable in config groups.

Example:

```
GROUP odd          1:N:2
GROUP even         0:N:2
GROUP "odd even"  odd,even
```

**OS-COUNTER-DELAY****Syntax:** <delay>**Variable:** VT\_OS\_COUNTER\_DELAY**Default:** 1 second

If OS counters have been enabled with the **COUNTER** configuration option, then these counters will be sampled every <delay> seconds. As usual, the value may also be specified with units, 1m for one minute, for example.

**DEADLOCK-TIMEOUT****Syntax:** <delay>**Variable:** VT\_DEADLOCK\_TIMEOUT**Default:** 1 minute

If ITC observes no progress for this amount of time in any process, then it assumes that a deadlock has occurred, stops the application and writes a trace file.

As usual, the value may also be specified with units, 1m for one minute, for example.

**DEADLOCK-WARNING****Syntax:** <delay>**Variable:** VT\_DEADLOCK\_WARNING**Default:** 5 minutes

If on average the MPI processes are stuck in their last MPI call for more than this threshold, then a GLOBAL:DEADLOCK:NO\_PROGRESS warning is generated. This is a sign of a load imbalance or a deadlock which cannot be detected because at least one process polls for progress instead of blocking inside an MPI call.

As usual, the value may also be specified with units, 1m for one minute, for example.

**HANDLE-SIGNALS****Syntax:** <triplets of signal numbers>**Variable:** VT\_HANDLE\_SIGNALS**Default:** none in libVTcs, all in other fail-safe libs

This option controls whether ITC replaces a signal handler previously set by the application or runtime system with its own handler. libVTcs by default does not override handlers, while the fail-safe MPI tracing libraries do: otherwise they would not be able to log the reason for an abort by MPI.

Using the standard triplet notation you can both list individual signals (Example: "3") as well as a whole range of signals ("3,10:100").

**ALTSTACK****Syntax:** [on|off]**Variable:** `VT_ALTSTACK`

Handling segfaults due to a stack overflow requires that the signal handler runs on an alternative stack, otherwise it will just segfault again, causing the process to be terminated.

Because installing an alternative signal handler affects application behavior, it is normally not done. Only for MPI correctness checking it is enabled if it is known to work.

**TIMER****Syntax:** <timer name or LIST>**Variable:** `VT_TIMER`**Default:** `gettimeofday`

ITC can use different sources for time stamps. The availability of the different timers may depend on the actual machine configuration.

To get a full list, link an application against ITC, then run it with this configuration option set to "LIST". By setting the verbosity to 2 or higher you get output for each node in a cluster. In this mode no error messages are printed if initialization of a certain timer fails, it is simply listed as unavailable. To see error messages run the program with `TIMER` set to the name of the timer that you want to use.

**TIMER-SKIP****Syntax:** <number> 0**Variable:** `VT_TIMER_SKIP`

number of intermediate clock sample points which are to be skipped when running the `timertest` program: they then serve as check that the interpolation makes sense

**SYNC-MAX-DURATION****Syntax:** <duration>**Variable:** `VT_SYNC_MAX_DURATION`**Default:** 1 minute

ITC can use either a barrier at the beginning and the end of the program run to take synchronized time stamps on processes or it can use a more advanced algorithm based on statistical analysis of message round-trip times.

This options enables this algorithm by setting the maximum number of seconds that ITC exchanges messages among processes. A value less or equal zero disables the statistical algorithm.

The default duration is much longer than actually needed, because usually the maximum number of messages (set via `SYNC-MAX-MESSAGES`) will be reached first. This setting mostly acts as a safe-guard against excessive synchronization times, at the cost of potentially reducing the quality of clock synchronization when reaching it and then sending less messages.

**SYNC-MAX-MESSAGES****Syntax:** <message number>**Variable:** `VT_SYNC_MAX_MESSAGES`**Default:** 100

If `SYNC-MAX-DURATION` is larger than zero and thus statistical analysis of message round-trip times is done, then this option limits the number of message exchanges.

**SYNC-PERIOD****Syntax:** <duration>**Variable:** `VT_SYNC_PERIOD`**Default:** -1 seconds = disabled





## 9.5. SUPPORTED DIRECTIVES

---

If clock synchronization via message exchanges is enabled (the default), then ITC can be told to do message exchanges during the application run automatically. By default this is disabled and needs to be enabled by setting this option to a positive time value.

The message exchange is done by a background thread and thus needs a means of communication which can execute in parallel to the application's communication, therefore it is not supported by the normal MPI tracing library libVT.

### SYNCD-CLUSTER

**Syntax:** [on|off]

**Variable:** `VT_SYNCD_CLUSTER`

**Default:** off

Use this setting to override whether ITC treats the clock of all processes anywhere in the cluster as synchronized or not. Whether ITC makes that assumption depends on the selected time source.

### SYNCD-HOST

**Syntax:** [on|off]

**Variable:** `VT_SYNCD_HOST`

**Default:** off

Use this setting to override whether ITC treats the clock of all processes on the same node as synchronized or not. Whether ITC makes that assumption depends on the selected time source.

If `SYNCD-CLUSTER` is on, then this option is ignored.

### NMCMC

**Syntax:** `<command + args> "nm -P"`

**Variable:** `VT_NMCMC`

If function tracing with GCC 2.95.2+'s `-finstrument-function` is used, then ITC will be called at function entry/exit. Before logging these events it has to map from the function's address in the executable to its name.

This is done with the help of an external program, usually `nm`. You can override the default if it is not appropriate on your system. The executable's filename (including the path) is appended at the end of the command, and the command is expected to print the result to stdout in the format defined for POSIX.2 `nm`.

### UNIFY-SYMBOLS

**Syntax:** [on|off]

**Variable:** `VT_UNIFY_SYMBOLS`

**Default:** on

During post-processing ITC unifies the ids assigned to symbols on different processes. This step is redundant if (and only if) all processes define all symbols in exactly the same order with exactly the same names. As ITC cannot recognize that automatically this unification can be disabled by the user to reduce the time required for trace file generation. Make sure that your program really defines symbols consistently when using this option!

### UNIFY-SCLS

**Syntax:** [on|off]

**Variable:** `VT_UNIFY_SCLS`

**Default:** on

Same as `UNIFY-SYMBOLS` for SCLs.

### UNIFY-GROUPS

**Syntax:** [on|off]

**Variable:** `VT_UNIFY_GROUPS`



**Default:** on

Same as [UNIFY-SYMBOLS](#) for groups.

### UNIFY-COUNTERS

**Syntax:** [on|off]

**Variable:** [VT\\_UNIFY\\_COUNTERS](#)

**Default:** on

Same as [UNIFY-SYMBOLS](#) for counters.

## 9.6 How to Use the Filtering Facility

A single configuration file can contain an arbitrary number of filter directives that are evaluated whenever a state is defined. Since they are evaluated in the same order as specified in the configuration file, the last filter matching a state determines whether it is traced or not. This scheme makes it easily possible to focus on a small set of activities without having to specify complex matching patterns. Being able to turn entire activities (groups of states) on or off helps to limit the number of filter directives. All matching is case-insensitive.

Example:

```
# disable all MPI activities
ACTIVITY MPI OFF
# enable all send routines in MPI
STATE MPI:*send ON
# except MPI_Bsend
SYMBOL MPI_bsend OFF
# enable receives
SYMBOL MPI_recv ON
# and all test routines
SYMBOL MPI_test* ON
# and all wait routines, recording locations of four calling levels
SYMBOL MPI_wait* 4
# enable all activities in the Application class, without locations
ACTIVITY Application 0
```

In effect, all activities in the class Application, all MPI send routines except MPI\_Bsend(), and all receive, test and wait routines will be traced. All other MPI routines will not be traced.

Because inserting line break into environment variables can be difficult, the SYMBOL/STATE/ACTIVITY rules also support multiple entries per line or environment variable, as in:

```
SYMBOL MPI_* off MPI_Barrier on
```

Beside filtering specific activities or states it is also possible to filter by process ranks in MPI\_COMM\_WORLD. This can be done with the configuration file directive [PROCESS](#). The value of this option is a comma separated list of Fortran 90-style triplets. The formal definition is as follows:

```
<PARAMETER-LIST> := <TRIPLET>[ ,<TRIPLET> , ... ]
<TRIPLET> := <LOWER-BOUND>[ :<UPPER-BOUND>[ :<INCREMENT> ] ]
```

The default value for <UPPER-BOUND> is N (equals size of MPI\_COMM\_WORLD) and the default value for <INCREMENT> is 1.

For instance changing tracing only on even process ranks and on process 1 the triplet list is: 0:N:2,1:1:1, where N is the total number of processes. All processes are enabled by default, so you have to disable all of them first ("[PROCESS](#) 0:N OFF") before enabling a certain subset again. For SMP clusters, the "[CLUSTER](#)" filter option can be used to filter for particular SMP nodes.



## 9.7. THE PROTOCOL FILE

The STATE/ACTIVITY/SYMBOL rule body may offer even finer control over tracing depending on the features available on the current platform:

- Special filter rules make it possible to turn tracing on and off during runtime when certain states (aka functions) are entered or left. In contrast to `VT_traceon/off()` no changes in the source code are required for this. So called "actions" are "triggered" by entering or leaving a state and executed before the state is logged.
- If folding is enabled for a function, then this function is traced, but not any of those that it calls. If you want to see one of these functions, then unfold it.
- Counter sampling can be disabled for states.

Here's the formal specification:

```
<SCLRANGE>      := on|off|<trace>|<skip>:<trace>
<PATTERN>       := <state or function wild-card as defined for STATE>
<SCOPE_NAME>    := [<class name as string>:]<scope name as string>

<ACTION>        := traceon|traceoff|restore|none|
                  begin_scope <SCOPE_NAME>|end_scope <SCOPE_NAME>
<TRIGGER>       := [<TRIPLET>] <ACTION> [<ACTION>]
<ENTRYTRIGGER> := entry <TRIGGER>
<EXITTRIGGER>   := exit <TRIGGER>
<COUNTERSTATE> := counteron|counteroff
<FOLDING>       := fold|unfold
<CALLER>        := caller <PATTERN>
<RULEENTRY>     := <SCLRANGE>|<ENTRYTRIGGER>|<EXITTRIGGER>|
                  <COUNTERSTATE>|<FOLDING>|<CALLER>
```

The filter body of a filter may still consist of a `<SCLRANGE>` which is valid for every instance of the state (as described above), but also of a counter state specification, an `<ENTRYTRIGGER>` which is checked each time the state is entered and an `<EXITTRIGGER>` for leaving it. The caller pattern, if given, is an additional criteria for the calling function that has to match before the entry, exit or folding actions are executed. The body may have any combination of these entries, separated by commas, as long as no entry is given more than once per rule.

Counter sampling can generate a lot of data, and some of it may not be relevant for every function. By default all enabled counters are sampled whenever a state change occurs. The "COUNTERON/OFF" rule entry modifies this for those states that match the pattern. There is no control over which counters are sampled on a per-state basis, though, you can only enable or disable sampling completely per state. This example disables counter sampling in any state, then enables it again for MPI functions:

```
SYMBOL      *      COUNTEROFF
ACTIVITY MPI COUNTERON
```

## 9.7 The Protocol File

The protocol file has the same syntax and entries as a ITC configuration file. Its extension is `.prot`, with the basename being the same as the tracefile. It lists all options with their values used when the program was started, thus it can be used to restart an application with exactly the same options.

All options are listed, even if they were not present in the original configuration. This way you can find about f.i. the default value of `SYNCED-HOST/CLUSTER` on your machine. Comments tell where the value came from (default, modified by user, default value set explicitly by the user).



Besides the configuration entries, the protocol file contains some entries that are only informative. They are all introduced by the keyword INFO. The following information entries are currently supported:

**INFO NUMPROCS**

**Syntax:** <num>

Number of processes in MPI.COMM.WORLD.

**INFO CLUSTERDEF**

**Syntax:** <name> [<rank>:<pid>]+

For clustered systems, the processes with Unix process id <pid> and rank in MPI.COMM.WORLD <rank> are running on the cluster node <name>. There will be one line per cluster node.

**INFO PROCESS**

**Syntax:** <rank> "<hostname>" "<IP>" <pid>

For each process identified by its MPI <rank>, the <hostname> as returned by gethostname(), the <pid> from getpid() and all <IP> addresses that <hostname> translates into with gethostbyname() are given. IP addresses are converted to string with ntoa() and separated with commas. Both hostname and IP string might be empty, if the information was not available.

**INFO BINMODE**

**Syntax:** <mode>

Records the floating-point and integer-length execution mode used by the application.

There may be other INFO entries that represent statistical data about the program run. Their syntax is explained in the file itself.



---

## Appendix A

# Copyright and Licenses

The MPI datatype hash code was developed by Julien Langou and George Bosilca, University of Tennessee, and is used with permission under the following license:

```
Copyright (c) 1992-2007 The University of Tennessee. All rights reserved.  
$COPYRIGHT$
```

```
Additional copyrights may follow
```

```
$HEADER$
```

```
Redistribution and use in source and binary forms, with or without  
modification, are permitted provided that the following conditions are  
met:
```

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
  
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer listed in this license in the documentation and/or other materials provided with the distribution.
  
- Neither the name of the copyright holders nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

```
THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS  
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT  
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR  
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT  
OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,  
SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT  
LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,  
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY  
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT  
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE  
OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
```

# Index

- activity
  - command line switch definition, [22](#)
- config
  - command line switch definition, [21](#)
- convert
  - command line switch definition, [66](#)
- dump
  - command line switch definition, [66](#)
- executable
  - command line switch definition, [21](#)
- extended-vtf
  - command line switch definition, [67](#)
- filter
  - command line switch definition, [19](#)
- insert
  - command line switch definition, [20](#)
- list
  - command line switch definition, [19](#)
- logfile-format
  - command line switch definition, [67](#)
- logfile-name
  - command line switch definition, [67](#)
- matched-vtf
  - command line switch definition, [68](#)
- max-threads
  - command line switch definition, [21](#)
- move
  - command line switch definition, [66](#)
- mpi
  - command line switch definition, [20](#)
- print-errors
  - command line switch definition, [66](#)
- print-files
  - command line switch definition, [66](#)
- print-statistics
  - command line switch definition, [66](#)
- print-threads
  - command line switch definition, [66](#)
- profile
  - command line switch definition, [20](#)
- remove
  - command line switch definition, [66](#)
- request
  - command line switch definition, [67](#)
- run
  - command line switch definition, [19](#)
- state
  - command line switch definition, [21](#)
- symbol
  - command line switch definition, [22](#)
- ticks
  - command line switch definition, [67](#)
- use-debug
  - command line switch definition, [19](#)
- verbose
  - command line switch definition, [21](#), [68](#)
- ~VT\_Function
  - VT\_Function, [100](#)
- ~VT\_Region
  - VT\_Region, [101](#)
- \_VT\_CommIDs
  - VT.h, [91](#)
- \_VT\_ErrorCode
  - VT.h, [72](#)
- \_VT\_OpTypes
  - VT.h, [93](#)
- ALTSTACK
  - config directive definition, [114](#)
- AUTOFLUSH
  - config directive definition, [110](#)
- begin
  - VT\_Region, [101](#), [102](#)
- CHECK
  - config directive definition, [106](#)
- CHECK-LEAK-REPORT-SIZE
  - config directive definition, [108](#)
- CHECK-MAX-DATATYPES
  - config directive definition, [108](#)
- CHECK-MAX-ERRORS
  - config directive definition, [106](#)
- CHECK-MAX-PENDING
  - config directive definition, [107](#)
- CHECK-MAX-REPORTS
  - config directive definition, [107](#)
- CHECK-MAX-REQUESTS
  - config directive definition, [107](#)

- CHECK-SUPPRESSION-LIMIT
  - config directive definition, [107](#)
- CHECK-TIMEOUT
  - config directive definition, [107](#)
- CLUSTER
  - config directive definition, [110](#)
- COUNTER
  - config directive definition, [108](#)
- CURRENT-DIR
  - config directive definition, [105](#)
- DEADLOCK-TIMEOUT
  - config directive definition, [113](#)
- DEADLOCK-WARNING
  - config directive definition, [113](#)
- DETAILED-STATES
  - config directive definition, [108](#)
- end
  - VT\_Region, [102](#)
- ENTER-USERCODE
  - config directive definition, [108](#)
- ENVIRONMENT
  - config directive definition, [112](#)
- environment variable
  - VT\_ADD\_LIBS, [6](#)
  - VT\_CONFIG, [9](#)
  - VT\_CONFIG\_RANK, [9](#)
  - VT\_DLL\_DIR, [6](#)
  - VT\_FMPI\_DLL, [6](#)
  - VT\_LIB\_DIR, [6](#)
  - VT\_MPI, [6](#)
  - VT\_MPI\_DLL, [6](#)
  - VT\_ROOT, [6](#)
  - VT\_SLIB\_DIR, [6](#)
- EXTENDED-VTF
  - config directive definition, [105](#)
- FLUSH-PID
  - config directive definition, [111](#)
- FLUSH-PREFIX
  - config directive definition, [111](#)
- GetHandle
  - VT\_FuncDef, [98](#)
  - VT\_SclDef, [98](#)
- GROUP
  - config directive definition, [113](#)
- HANDLE-SIGNALS
  - config directive definition, [113](#)
- INFO BINMODE
  - config directive definition, [118](#)
- INFO CLUSTERDEF
  - config directive definition, [118](#)
- INFO NUMPROCS
  - config directive definition, [118](#)
- INFO PROCESS
  - config directive definition, [118](#)
- INTERNAL-MPI
  - config directive definition, [108](#)
- LOGFILE-FORMAT
  - config directive definition, [105](#)
- LOGFILE-NAME
  - config directive definition, [104](#)
- LOGFILE-PREFIX
  - config directive definition, [105](#)
- LOGFILE-RANK
  - config directive definition, [106](#)
- MEM-BLOCKSIZE
  - config directive definition, [110](#)
- MEM-FLUSHBLOCKS
  - config directive definition, [110](#)
- MEM-INFO
  - config directive definition, [110](#)
- MEM-MAXBLOCKS
  - config directive definition, [110](#)
- MEM-MINBLOCKS
  - config directive definition, [110](#)
- MEM-OVERWRITE
  - config directive definition, [111](#)
- NMCMD
  - config directive definition, [115](#)
- OS-COUNTER-DELAY
  - config directive definition, [113](#)
- PCTRACE
  - config directive definition, [109](#)
- PCTRACE-CACHE
  - config directive definition, [109](#)
- PCTRACE-FAST
  - config directive definition, [109](#)
- PLUGIN
  - config directive definition, [106](#)
- PROCESS
  - config directive definition, [109](#)
- PROGNAME
  - config directive definition, [105](#)
- PROTOFILE-NAME
  - config directive definition, [105](#)
- STATISTICS
  - config directive definition, [112](#)
- STF-CHUNKSIZE
  - config directive definition, [112](#)

- STF-PROCS-PER-FILE
  - config directive definition, [112](#)
- STF-USE-HW-STRUCTURE
  - config directive definition, [112](#)
- STOPFILE-NAME
  - config directive definition, [106](#)
- SYNC-MAX-DURATION
  - config directive definition, [114](#)
- SYNC-MAX-MESSAGES
  - config directive definition, [114](#)
- SYNC-PERIOD
  - config directive definition, [114](#)
- SYNCED-CLUSTER
  - config directive definition, [115](#)
- SYNCED-HOST
  - config directive definition, [115](#)
- TIMER
  - config directive definition, [114](#)
- TIMER-SKIP
  - config directive definition, [114](#)
- UNIFY-COUNTERS
  - config directive definition, [116](#)
- UNIFY-GROUPS
  - config directive definition, [115](#)
- UNIFY-SCLS
  - config directive definition, [115](#)
- UNIFY-SYMBOLS
  - config directive definition, [115](#)
- VERBOSE
  - config directive definition, [106](#)
- VT.h
  - [\\_VT\\_CommIDs, 91](#)
  - [\\_VT\\_ErrorCode, 72](#)
  - [\\_VT\\_OpTypes, 93](#)
  - [VT\\_abort, 94](#)
  - [VT\\_attach, 96](#)
  - [VT\\_begin, 82](#)
  - [VT\\_begin\\_unordered, 93](#)
  - [VT\\_beginl, 82](#)
  - [VT\\_classdef, 80](#)
  - [VT\\_clientinit, 95](#)
  - [VT\\_COMM\\_INVALID, 91](#)
  - [VT\\_COMM\\_SELF, 91](#)
  - [VT\\_COMM\\_WORLD, 91](#)
  - [VT\\_COUNT\\_ABSVAL, 89](#)
  - [VT\\_COUNT\\_DATA, 88](#)
  - [VT\\_COUNT\\_DISPLAY, 89](#)
  - [VT\\_COUNT\\_FLOAT, 88](#)
  - [VT\\_COUNT\\_INTEGER, 88](#)
  - [VT\\_COUNT\\_INTEGER64, 88](#)
  - [VT\\_COUNT\\_RATE, 89](#)
  - [VT\\_COUNT\\_SCOPE, 89](#)
  - [VT\\_COUNT\\_VALID\\_AFTER, 89](#)
  - [VT\\_COUNT\\_VALID\\_BEFORE, 89](#)
  - [VT\\_COUNT\\_VALID\\_POINT, 89](#)
  - [VT\\_COUNT\\_VALID\\_SAMPLE, 89](#)
  - [VT\\_CountData, 88](#)
  - [VT\\_countdef, 89](#)
  - [VT\\_CountDisplay, 89](#)
  - [VT\\_CountScope, 89](#)
  - [VT\\_countval, 90](#)
  - [VT\\_end, 83](#)
  - [VT\\_end\\_unordered, 94](#)
  - [VT\\_endl, 83](#)
  - [VT\\_enter, 83](#)
  - [VT\\_enterstate, 83](#)
  - [VT\\_ERR\\_BADARG, 72](#)
  - [VT\\_ERR\\_BADFILE, 72](#)
  - [VT\\_ERR\\_BADFORMAT, 72](#)
  - [VT\\_ERR\\_BADINDEX, 72](#)
  - [VT\\_ERR\\_BADKIND, 72](#)
  - [VT\\_ERR\\_BADREQUEST, 72](#)
  - [VT\\_ERR\\_BADSCL, 72](#)
  - [VT\\_ERR\\_BADSCLID, 72](#)
  - [VT\\_ERR\\_BADSYMBOLID, 72](#)
  - [VT\\_ERR\\_COMM, 72](#)
  - [VT\\_ERR\\_FLUSH, 72](#)
  - [VT\\_ERR\\_IGNORE, 72](#)
  - [VT\\_ERR\\_INV, 72](#)
  - [VT\\_ERR\\_NOLICENSE, 72](#)
  - [VT\\_ERR\\_NOMEMORY, 72](#)
  - [VT\\_ERR\\_NOTHREADS, 72](#)
  - [VT\\_ERR\\_NOTIMPLEMENTED, 72](#)
  - [VT\\_ERR\\_NOTINITIALIZED, 72](#)
  - [VT\\_finalize, 74](#)
  - [VT\\_flush, 76](#)
  - [VT\\_funcdef, 81](#)
  - [VT\\_get\\_parent, 96](#)
  - [VT\\_getprocid, 87](#)
  - [VT\\_getrank, 74](#)
  - [VT\\_getthrank, 75](#)
  - [VT\\_getthreadid, 87](#)
  - [VT\\_Group, 86](#)
  - [VT\\_GROUP\\_CLUSTER, 86](#)
  - [VT\\_GROUP\\_PROCESS, 86](#)
  - [VT\\_GROUP\\_THREAD, 86](#)
  - [VT\\_groupdef, 87](#)
  - [VT\\_initialize, 73](#)
  - [VT\\_leave, 83](#)
  - [VT\\_log\\_msgevent, 92](#)
  - [VT\\_log\\_op, 92](#)
  - [VT\\_log\\_opevent, 92](#)
  - [VT\\_log\\_recvmsg, 91](#)
  - [VT\\_log\\_sendmsg, 91](#)
  - [VT\\_ME, 86](#)



- VT\_NOCLASS, [81](#)
- VT\_NOSCL, [78](#)
- VT\_OK, [72](#)
- VT\_OP\_ALLGATHER, [93](#)
- VT\_OP\_ALLGATHERV, [93](#)
- VT\_OP\_ALLREDUCE, [93](#)
- VT\_OP\_ALLTOALL, [93](#)
- VT\_OP\_ALLTOALLV, [93](#)
- VT\_OP\_BARRIER, [93](#)
- VT\_OP\_BCAST, [93](#)
- VT\_OP\_COUNT, [93](#)
- VT\_OP\_GATHER, [93](#)
- VT\_OP\_GATHERV, [93](#)
- VT\_OP\_INVALID, [93](#)
- VT\_OP\_REDUCE, [93](#)
- VT\_OP\_REDUCE\_SCATTER, [93](#)
- VT\_OP\_SCAN, [93](#)
- VT\_OP\_SCATTER, [93](#)
- VT\_OP\_SCATTERV, [93](#)
- VT\_registernamed, [74](#)
- VT\_registerthread, [74](#)
- VT\_SCL\_DEF\_CXX, [98](#)
- VT\_scldef, [77](#)
- VT\_sclstack, [78](#)
- VT\_scopebegin, [86](#)
- VT\_scopedef, [85](#)
- VT\_scopeend, [86](#)
- VT\_serverinit, [95](#)
- VT\_symdef, [81](#)
- VT\_symstate, [76](#)
- VT\_thisloc, [79](#)
- VT\_timestamp, [77](#)
- VT\_timestart, [77](#)
- VT\_timesync, [48](#)
- VT\_traceoff, [75](#)
- VT\_traceon, [75](#)
- VT\_tracestate, [75](#)
- VT\_VERSION, [71](#)
- VT\_VERSION\_COMPATIBILITY, [71](#)
- VT\_wakeup, [85](#)
- VT\_ALTSTACK
  - env variable definition, [114](#)
- VT\_AUTOFLUSH
  - env variable definition, [110](#)
- VT\_CHECK
  - env variable definition, [106](#)
- VT\_CHECK\_LEAK\_REPORT\_SIZE
  - env variable definition, [108](#)
- VT\_CHECK\_MAX\_DATATYPES
  - env variable definition, [108](#)
- VT\_CHECK\_MAX\_ERRORS
  - env variable definition, [106](#)
- VT\_CHECK\_MAX\_PENDING
  - env variable definition, [107](#)
- VT\_CHECK\_MAX\_REPORTS
  - env variable definition, [107](#)
- VT\_CHECK\_MAX\_REQUESTS
  - env variable definition, [107](#)
- VT\_CHECK\_SUPPRESSION\_LIMIT
  - env variable definition, [107](#)
- VT\_CHECK\_TIMEOUT
  - env variable definition, [107](#)
- VT\_CLUSTER
  - env variable definition, [110](#)
- VT\_COUNTER
  - env variable definition, [108](#)
- VT\_CURRENT\_DIR
  - env variable definition, [105](#)
- VT\_DEADLOCK\_TIMEOUT
  - env variable definition, [113](#)
- VT\_DEADLOCK\_WARNING
  - env variable definition, [113](#)
- VT\_DETAILED\_STATES
  - env variable definition, [108](#)
- VT\_ENTER\_USERCODE
  - env variable definition, [108](#)
- VT\_ENVIRONMENT
  - env variable definition, [112](#)
- VT\_EXTENDED\_VTF
  - env variable definition, [105](#)
- VT\_FLUSH\_PID
  - env variable definition, [111](#)
- VT\_FLUSH\_PREFIX
  - env variable definition, [111](#)
- VT\_GROUP
  - env variable definition, [113](#)
- VT\_HANDLE\_SIGNALS
  - env variable definition, [113](#)
- VT\_INTERNAL\_MPI
  - env variable definition, [108](#)
- VT\_LOGFILE\_FORMAT
  - env variable definition, [105](#)
- VT\_LOGFILE\_NAME
  - env variable definition, [104](#)
- VT\_LOGFILE\_PREFIX
  - env variable definition, [105](#)
- VT\_LOGFILE\_RANK
  - env variable definition, [106](#)
- VT\_MEM\_BLOCKSIZE
  - env variable definition, [110](#)
- VT\_MEM\_FLUSHBLOCKS
  - env variable definition, [110](#)
- VT\_MEM\_INFO
  - env variable definition, [110](#)
- VT\_MEM\_MAXBLOCKS
  - env variable definition, [110](#)
- VT\_MEM\_MINBLOCKS
  - env variable definition, [110](#)

- VT\_MEM\_OVERWRITE
  - env variable definition, [111](#)
- VT\_NMCMD
  - env variable definition, [115](#)
- VT\_OS\_COUNTER\_DELAY
  - env variable definition, [113](#)
- VT\_PCTRACE
  - env variable definition, [109](#)
- VT\_PCTRACE\_CACHE
  - env variable definition, [109](#)
- VT\_PCTRACE\_FAST
  - env variable definition, [109](#)
- VT\_PLUGIN
  - env variable definition, [106](#)
- VT\_PROCESS
  - env variable definition, [109](#)
- VT\_PROGNAME
  - env variable definition, [105](#)
- VT\_PROTOFILE\_NAME
  - env variable definition, [105](#)
- VT\_STATISTICS
  - env variable definition, [112](#)
- VT\_STF\_CHUNKSIZE
  - env variable definition, [112](#)
- VT\_STF\_PROCS\_PER\_FILE
  - env variable definition, [112](#)
- VT\_STF\_USE\_HW\_STRUCTURE
  - env variable definition, [112](#)
- VT\_STOPFILE\_NAME
  - env variable definition, [106](#)
- VT\_SYNC\_MAX\_DURATION
  - env variable definition, [114](#)
- VT\_SYNC\_MAX\_MESSAGES
  - env variable definition, [114](#)
- VT\_SYNC\_PERIOD
  - env variable definition, [114](#)
- VT\_SYNCED\_CLUSTER
  - env variable definition, [115](#)
- VT\_SYNCED\_HOST
  - env variable definition, [115](#)
- VT\_TIMER
  - env variable definition, [114](#)
- VT\_TIMER\_SKIP
  - env variable definition, [114](#)
- VT\_UNIFY\_COUNTERS
  - env variable definition, [116](#)
- VT\_UNIFY\_GROUPS
  - env variable definition, [115](#)
- VT\_UNIFY\_SCLS
  - env variable definition, [115](#)
- VT\_UNIFY\_SYMBOLS
  - env variable definition, [115](#)
- VT\_VERBOSE
  - env variable definition, [106](#)
- VT\_ADD\_LIBS
  - environment variable, [6](#)
- VT\_CONFIG
  - environment variable, [9](#)
- VT\_CONFIG\_RANK
  - environment variable, [9](#)
- VT\_FMPI\_DLL
  - environment variable, [6](#)
- VT\_LIB\_DIR
  - environment variable, [6](#)
- VT\_MPI
  - environment variable, [6](#)
- VT\_MPI\_DLL
  - environment variable, [6](#)
- VT\_ROOT
  - environment variable, [6](#)
- VT\_SLIB\_DIR
  - environment variable, [6](#)
- VT\_abort
  - VT.h, [94](#)
- VT\_attach
  - VT.h, [96](#)
- VT\_begin
  - VT.h, [82](#)
- VT\_begin\_unordered
  - VT.h, [93](#)
- VT\_beginl
  - VT.h, [82](#)
- VT\_classdef
  - VT.h, [80](#)
- VT\_clientinit
  - VT.h, [95](#)
- VT\_COMM\_INVALID
  - VT.h, [91](#)
- VT\_COMM\_SELF
  - VT.h, [91](#)
- VT\_COMM\_WORLD
  - VT.h, [91](#)
- VT\_COUNT\_ABSVAL
  - VT.h, [89](#)
- VT\_COUNT\_DATA
  - VT.h, [88](#)
- VT\_COUNT\_DISPLAY
  - VT.h, [89](#)
- VT\_COUNT\_FLOAT
  - VT.h, [88](#)
- VT\_COUNT\_INTEGER
  - VT.h, [88](#)
- VT\_COUNT\_INTEGER64
  - VT.h, [88](#)
- VT\_COUNT\_RATE
  - VT.h, [89](#)
- VT\_COUNT\_SCOPE
  - VT.h, [89](#)

VT\_COUNT\_VALID\_AFTER  
VT.h, [89](#)

VT\_COUNT\_VALID\_BEFORE  
VT.h, [89](#)

VT\_COUNT\_VALID\_POINT  
VT.h, [89](#)

VT\_COUNT\_VALID\_SAMPLE  
VT.h, [89](#)

VT\_CountData  
VT.h, [88](#)

VT\_countdef  
VT.h, [89](#)

VT\_CountDisplay  
VT.h, [89](#)

VT\_CountScope  
VT.h, [89](#)

VT\_countval  
VT.h, [90](#)

VT\_end  
VT.h, [83](#)

VT\_end\_unordered  
VT.h, [94](#)

VT\_endl  
VT.h, [83](#)

VT\_enter  
VT.h, [83](#)

VT\_enterstate  
VT.h, [83](#)

VT\_ERR\_BADARG  
VT.h, [72](#)

VT\_ERR\_BADFILE  
VT.h, [72](#)

VT\_ERR\_BADFORMAT  
VT.h, [72](#)

VT\_ERR\_BADINDEX  
VT.h, [72](#)

VT\_ERR\_BADKIND  
VT.h, [72](#)

VT\_ERR\_BADREQUEST  
VT.h, [72](#)

VT\_ERR\_BADSCL  
VT.h, [72](#)

VT\_ERR\_BADSCLID  
VT.h, [72](#)

VT\_ERR\_BADSYMBOLID  
VT.h, [72](#)

VT\_ERR\_COMM  
VT.h, [72](#)

VT\_ERR\_FLUSH  
VT.h, [72](#)

VT\_ERR\_IGNORE  
VT.h, [72](#)

VT\_ERR\_INV  
VT.h, [72](#)

VT\_ERR\_NOLICENSE  
VT.h, [72](#)

VT\_ERR\_NOMEMORY  
VT.h, [72](#)

VT\_ERR\_NOTHREADS  
VT.h, [72](#)

VT\_ERR\_NOTIMPLEMENTED  
VT.h, [72](#)

VT\_ERR\_NOTINITIALIZED  
VT.h, [72](#)

VT\_finalize  
VT.h, [74](#)

VT\_flush  
VT.h, [76](#)

VT\_FuncDef  
VT\_FuncDef, [98](#)

VT\_FuncDef, [97](#)  
GetHandle, [98](#)  
VT\_FuncDef, [98](#)

VT\_funcdef  
VT.h, [81](#)

VT\_Function, [99](#)  
~VT\_Function, [100](#)  
VT\_Function, [99](#)

VT\_get\_parent  
VT.h, [96](#)

VT\_getprocid  
VT.h, [87](#)

VT\_getrank  
VT.h, [74](#)

VT\_getthrank  
VT.h, [75](#)

VT\_getthreadid  
VT.h, [87](#)

VT\_Group  
VT.h, [86](#)

VT\_GROUP\_CLUSTER  
VT.h, [86](#)

VT\_GROUP\_PROCESS  
VT.h, [86](#)

VT\_GROUP\_THREAD  
VT.h, [86](#)

VT\_groupdef  
VT.h, [87](#)

VT\_initialize  
VT.h, [73](#)

VT\_leave  
VT.h, [83](#)

VT\_log\_msgevent  
VT.h, [92](#)

VT\_log\_op  
VT.h, [92](#)

VT\_log\_opevent  
VT.h, [92](#)



VT\_log\_recvmsg  
VT.h, 91

VT\_log\_sendmsg  
VT.h, 91

VT\_ME  
VT.h, 86

VT\_NOCLASS  
VT.h, 81

VT\_NOSCL  
VT.h, 78

VT\_OK  
VT.h, 72

VT\_OP\_ALLGATHER  
VT.h, 93

VT\_OP\_ALLGATHERV  
VT.h, 93

VT\_OP\_ALLREDUCE  
VT.h, 93

VT\_OP\_ALLTOALL  
VT.h, 93

VT\_OP\_ALLTOALLV  
VT.h, 93

VT\_OP\_BARRIER  
VT.h, 93

VT\_OP\_BCAST  
VT.h, 93

VT\_OP\_COUNT  
VT.h, 93

VT\_OP\_GATHER  
VT.h, 93

VT\_OP\_GATHERV  
VT.h, 93

VT\_OP\_INVALID  
VT.h, 93

VT\_OP\_REDUCE  
VT.h, 93

VT\_OP\_REDUCE\_SCATTER  
VT.h, 93

VT\_OP\_SCAN  
VT.h, 93

VT\_OP\_SCATTER  
VT.h, 93

VT\_OP\_SCATTERV  
VT.h, 93

VT\_Region, 100  
~VT\_Region, 101  
begin, 101, 102  
end, 102  
VT\_Region, 100, 101

VT\_registernamed  
VT.h, 74

VT\_registerthread  
VT.h, 74

VT\_SCL\_DEF\_CXX  
VT.h, 98

VT\_SclDef  
VT\_SclDef, 98

VT\_SclDef, 98  
GetHandle, 98  
VT\_SclDef, 98

VT\_scldef  
VT.h, 77

VT\_sclstack  
VT.h, 78

VT\_scopebegin  
VT.h, 86

VT\_scopedef  
VT.h, 85

VT\_scopeend  
VT.h, 86

VT\_serverinit  
VT.h, 95

VT\_symdef  
VT.h, 81

VT\_symstate  
VT.h, 76

VT\_thisloc  
VT.h, 79

VT\_timestamp  
VT.h, 77

VT\_timestart  
VT.h, 77

VT\_timesync  
VT.h, 48

VT\_traceoff  
VT.h, 75

VT\_traceon  
VT.h, 75

VT\_tracestate  
VT.h, 75

VT\_VERSION  
VT.h, 71

VT\_VERSION\_COMPATIBILITY  
VT.h, 71

VT\_wakeup  
VT.h, 85