

Note: It is recommended that the storage system is connected to a DHCP-enabled network to complete the software install.

Insert the Resource CD that shipped with your Intel® Entry Storage System SS4200-E into a computer connected to the same network as the storage system.


Note: If the Resource CD does not start automatically, navigate to the Resource CD and manually run install.exe. The storage system manager software must be installed on a computer that is on the same network as your storage system.

2 Proceed through the Installation Wizard.

Select Language and click OK to continue.




- 3 Select I accept the terms of the License Agreement on the license agreement screen. Click Next to continue.
- 4 Select location for the install and click **Next** to continue.



6 Click Install.



6 The Installation Complete screen will appear. Click on **Done**.



The storage system manager will open automatically in the browser. The Welcome screen will display.



8 Click Next to start the Setup Wizard.

Note: If your storage system is not

Setup instructions will display.

detected by the manager, the Hardware

Note: When attempting to connect, Microsoft Internet Explorer* may display a security certificate warning screen. If this occurs, click Yes or Accept to proceed.

